

| | | | | | | | | | | |
|--|--|--|--|--|--|--|--|--|--|------------------------------|
| TTTTTTTTT TTTTTTTTT TT TT TT TT TT TT TT TT TT TT TT | TTTTTTTTT TTTTTTTTT TT TT TT TT TT TT TT TT TT TT TT | YY YY YY YY YY YY YY YY YY YY YY YY YY | YY YY YY YY YY YY YY YY YY YY YY YY YY | SSSSSSSS SSSSSSSS SS SS SS SS SSSSSS SSSSSS SS SS SS SSSSSS SSSSSS | TTTTTTTTT TTTTTTTTT TT TT TT TT TT TT TT TT TT TT TT | RRRRRRRR RRRRRRRR RR RR RR RR RRRRRR RRRRRR RR RR RR RR RR RR RR | SSSSSSSS SSSSSSSS SS SS SS SS SSSSSS SSSSSS SS SS SS SSSSSS SSSSSS | TTTTTTTTT TTTTTTTTT TT TT TT TT TT TT TT TT TT TT TT TT | PPPPPPPP PPPPPPPP PP PP PP PP PPPPPP PPPPPP PP PP PP PP PP PP | |
| LL LL LL LL LL LL LL LL LL LL LL LL LL LLLLLLLLL LLLLLLLLL | IIIIII IIIIII II II II II II II II II II II II IIIIII IIIIII | SSSSSSSS SSSSSSSS SS SS SS SS SSSSSS SSSSSS SS SS SS SS SSSSSS SSSSSS | SSSSSSSS SSSSSSSS SS SS SS SS SSSSSS SSSSSS SS SS SS SS SSSSSS SSSSSS | | | | | | | |

| | | |
|------|------|--|
| (2) | 255 | Declarations |
| (3) | 281 | TTY\$STARTIO - START I/O OPERATION ON TERMINAL |
| (4) | 317 | START IO ACTION ROUTINES |
| (15) | 740 | TTY\$WRITESTARTIO - Starts or queues a write operation |
| (16) | 944 | TTY\$STARTOUTPUT - START OUTPUT OPERATION ON UNIT |
| (17) | 977 | TTY\$GETNXTWRITE - Start next write or restart read |
| (18) | 1042 | TTY\$WRITEDONE - Complete a write operation |
| (19) | 1172 | TTY\$WRITEPOST - QUEUE A WRITE COMPLETION |
| (22) | 1242 | TTY\$READONE - READ OPERATION DONE |
| (24) | 1409 | End of module |


```
0000 1 .TITLE TTYSTRSTP - Terminal driver start/stop I/O routines
0000 2 .IDENT 'V04-000'
0000 3
0000 4
0000 5 *****
0000 6
0000 7 *
0000 8 * COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
0000 9 * DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
0000 10 * ALL RIGHTS RESERVED.
0000 11 *
0000 12 * THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
0000 13 * ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
0000 14 * INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
0000 15 * COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
0000 16 * OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
0000 17 * TRANSFERRED.
0000 18 *
0000 19 * THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
0000 20 * AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
0000 21 * CORPORATION.
0000 22 *
0000 23 * DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
0000 24 * SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
0000 25 *
0000 26 *****
0000 27
0000 28 ++
0000 29 FACILITY:
0000 30
0000 31 VAX/VMS TERMINAL DRIVER
0000 32
0000 33 ABSTRACT:
0000 34
0000 35 THIS MODULE CONTAINS ROUTINES PERTAINING TO STARTING AND COMPLETING
0000 36 I/O REQUESTS.
0000 37
0000 38 AUTHOR:
0000 39
0000 40 R.HEINEN 10-OCT-1977
0000 41
0000 42 Revision history:
0000 43
0000 44 V03-030 M1R0450 MICHAEL I. ROSENBLUM 27-JUN-1984
0000 45 Add code to the free linefeed logic to account for PC_NOCRLF.
0000 46 Fix problem that causes the first linefeed typed on a
0000 47 read with no prompt to not be echoed.
0000 48
0000 49 V03-029 RKS0029 RICK SPITZ 10-APR-1984
0000 50 Enhance virtual terminal connect action routine to
0000 51 perform an implicit set mode operation.
0000 52
0000 53 V03-028 M1R0370 Michael I. Rosenblum 20-Mar-1984
0000 54 Put code in to fix problems with lines and prompts causing
0000 55 wrap. Fix bug that would cause FMS programs to crash the
0000 56 system.
0000 57
```

| | | | | | | |
|------|-----|---|---------|---------|--|-------------|
| 0000 | 58 | : | V03-027 | RKS0027 | RICK SPITZ | 05-MAR-1984 |
| 0000 | 59 | : | | | Enhance write post completion to handle the case | |
| 0000 | 60 | : | | | of a write completion with no current PUCB. | |
| 0000 | 61 | : | | | | |
| 0000 | 62 | : | V03-026 | MIR0310 | Michael I. Rosenblum | 09-Feb-1984 |
| 0000 | 63 | : | | | Fix bugs. | |
| 0000 | 64 | : | | | make sure setting nomodem on a modem terminal shuts down | |
| 0000 | 65 | : | | | the line. | |
| 0000 | 66 | : | | | | |
| 0000 | 67 | : | V03-025 | MIR0300 | Michael I. Rosenblum | 30-Jan-1984 |
| 0000 | 68 | : | | | Add input fallback | |
| 0000 | 69 | : | | | | |
| 0000 | 70 | : | V03-024 | MIR0085 | Michael I. Rosenblum | 26-Aug-1983 |
| 0000 | 71 | : | | | Remove references to DCL_OUTBND and DCL_CTRLC. | |
| 0000 | 72 | : | | | | |
| 0000 | 73 | : | V03-023 | MIR0082 | Michael I. Rosenblum | 19-Aug-1983 |
| 0000 | 74 | : | | | Make autxoff mode work with passall and ttsync. | |
| 0000 | 75 | : | | | Fix passthru to remain enabled after a read completes. | |
| 0000 | 76 | : | | | | |
| 0000 | 77 | : | V03-022 | MIR0080 | Michael I. Rosenblum | 28-Jul-1983 |
| 0000 | 78 | : | | | Move newline code into write done rather than TTYFDT | |
| 0000 | 79 | : | | | Reposition routines in the module. | |
| 0000 | 80 | : | | | | |
| 0000 | 81 | : | V03-021 | MIR0070 | Michael I. Rosenblum | 13-jul-1983 |
| 0000 | 82 | : | | | Fix bug that would cause TTY\$DISCONNECT to be called twice. | |
| 0000 | 83 | : | | | if a SETMODE with the HANGUP modifier was issued. | |
| 0000 | 84 | : | | | | |
| 0000 | 85 | : | V03-020 | MIR0051 | Michael I. Rosenblum | 23-Jun-1983 |
| 0000 | 86 | : | | | Fix missing literals in connect and disconnect code. | |
| 0000 | 87 | : | | | Check write active bit in getnextwrite to insure that | |
| 0000 | 88 | : | | | The write queue is not reordered. | |
| 0000 | 89 | : | | | | |
| 0000 | 90 | : | V03-019 | RKS0019 | RICK SPITZ | 7-JUN-1983 |
| 0000 | 91 | : | | | ADD CONNECT/DISCONNECT ACTION ROUTINES. | |
| 0000 | 92 | : | | | ENHANCE WRITE DONE FORK PROCESS TO ALWAYS USE REQCOM | |
| 0000 | 93 | : | | | IF THE WRITE IRP IS POINTED TO BY UCBSL_IRP | |
| 0000 | 94 | : | | | MAKE SURE LUCB IS NOT DETACHED AT THE ALTERNATE WRITE ENTRY. | |
| 0000 | 95 | : | | | REMOVE CTRL Y HANGUP CHECK, AS IT IS STILL DONE IN FDT. | |
| 0000 | 96 | : | | | | |
| 0000 | 97 | : | V03-018 | RKS0018 | RICK SPITZ | 16-MAY-1983 |
| 0000 | 98 | : | | | MOVE SEGMENTS OF CHARACTERISTICS FDT CODE TO TTYSTRSTP | |
| 0000 | 99 | : | | | TO ALLOW CLEAN DISCONNECT OF DISCONNECTED TERMINALS. | |
| 0000 | 100 | : | | | RESTORE LUCB FROM LUCB IN READ/WRITE DONE. | |
| 0000 | 101 | : | | | | |
| 0000 | 102 | : | V03-017 | MIR0050 | Michael I. Rosenblum | 11-May-1983 |
| 0000 | 103 | : | | | Remove code that special cased broadcasts. Allow the | |
| 0000 | 104 | : | | | data returned by timeout errors to be stored in the recall | |
| 0000 | 105 | : | | | buffer. Make write post complete broadcasts. | |
| 0000 | 106 | : | | | | |
| 0000 | 107 | : | V03-016 | MIR0030 | Michael I. Rosenblum | 30-Mar-1983 |
| 0000 | 108 | : | | | Integrate Read verification with the standard driver | |
| 0000 | 109 | : | | | Add support for alternate frame sizes. | |
| 0000 | 110 | : | | | | |
| 0000 | 111 | : | V03-015 | MIR0029 | Michael I. Rosenblum | 22-Mar-1983 |
| 0000 | 112 | : | | | Add field to the iosb when itemlist reads are used. | |
| 0000 | 113 | : | | | | |
| 0000 | 114 | : | V03-014 | RKS0014 | RICK SPITZ | 14-MAR-1983 |


```
0000 115 : ADD SUPPORT FOR LOGICAL UCB. NOTE THAT THE DRIVER
0000 116 : SWITCHES TO PHYSICAL UCB CONTEXT AT STARTIO ENTRY. IT
0000 117 : RESTORES LOGICAL UCB CONTEXT PRIOR TO RETURNING TO THE
0000 118 : SYSTEM.
0000 119 :
0000 120 : V03-013 MIR8026 Michael I. Rosenblum 14-Mar-1983
0000 121 : Fix bug in partail escape sequence processing.
0000 122 :
0000 123 : V03-012 MIR5026 Michael I. Rosenblum 10-Mar-1983
0000 124 : Fix security whole with command recall and the password
0000 125 : by not allowing noecho strings to be stored in the recall
0000 126 : buffer.
0000 127 :
0000 128 : V03-011 MIR1024 Michael I. Rosenblum 09-Mar-1983
0000 129 : Fix code in getnxtwrite to look at the read packet
0000 130 : rather than UCBSW_BCNT to find the number of characters
0000 131 : that have been read so far.
0000 132 :
0000 133 : V03-010 MIR0026 Michael I. Rosenblum 01-Mar-1983
0000 134 : Add code to save the results of the last read.
0000 135 :
0000 136 : V03-009 MIR0024 Michael I. Rosenblum 28-Jan-1983
0000 137 : Update code to use the new read packet format
0000 138 :
0000 139 : V03-008 MIR0023 Michael I. Rosenblum 24-Jan-1983
0000 140 : Read buffer was used after it was deallocated if a
0000 141 : Cancel was issued while EDITREAD state was in affect.
0000 142 : Changed READONE code to clear the edit read states
0000 143 : when a read is completed.
0000 144 :
0000 145 : V03-007 MIR0016 Michael I. Rosenblum 4-Jan-1983
0000 146 : Change TTY$STARTOUTPUT to use the UCB OUTYPE field to determine
0000 147 : the necessary action when TTY$GETNEXTCHAR is called. This change
0000 148 : should illiminate the checking the volitale condition code bits
0000 149 : that previously had the function of OUTYPE. For compatibility
0000 150 : purposes only we are setting the correct condition codes.
0000 151 :
0000 152 : V03-006 MIR0015 Michael I. Rosenblum 20-Dec-1982
0000 153 : Change TTY$V_ST_UNSQL and TTY$V_ST_GETAHD to TTY$V_FD_UNSQL
0000 154 : and TTY$V_FD_GETAHD, to reflect changes in the fork dispatcher
0000 155 : also change PORT_DISCONNECT call to refer to
0000 156 : CLASS_MODEM_DIS. Change all port calls to call the Class
0000 157 : driver jacket routines.
0000 158 :
0000 159 : V03-005 MIR0013 Michael I. Rosenblum 16-Dec-1982
0000 160 : Fix up refferences to new ucb structure
0000 161 :
0000 162 : V03-004 MIR0011 Michael I. Rosenblum 18-Nov-1982
0000 163 : Remove code that implimented HOLDSCREEN.
0000 164 :
0000 165 : V03-003 MIR0010 Michael I Rosenblum 09-Nov-1982
0000 166 : Move the address of the terminator mask, and the length
0000 167 : of the prompt string from the IRP into the terminal read
0000 168 : buffer.
0000 169 :
0000 170 : V03-002 ROW0077 Ralph O. Weber 27-MAR-1982
0000 171 : Change TTY$WRITEDONE to insure that eventhough UCBSW_IT_CURSOR
```

0000 172 : can now be bigger than UCBSW DEVBUSIZ, i.e. eventhough our
0000 173 : internal cursor position marker can virtually be beyond the
0000 174 : right-hand edge of the screen, the cursor-position value
0000 175 : returned in IOSB will never exceed the width of the screen.
0000 176 :
0000 177 : V03-001 JLV0202 Jake VanNoy 23-MAR-1982
0000 178 : Change MODHANGUP from NOMOD to PRIV_TO_MOD in Set
0000 179 : Mode/Char logic.
0000 180 : Correct alternate class name lookup.
0000 181 :
0000 182 : V02-045 RKS0045 RICK SPITZ 22-FEB-1982
0000 183 : Repair diagnostic function code logic.
0000 184 :
0000 185 : V02-044 RKS0044 RICK SPITZ 16-FEB-1982
0000 186 : Enhance broadcast logic to allow delay prior to
0000 187 : forcing output. Move setting of controls pending
0000 188 : to STOP2 timeout. This way user ^s can be distinguished
0000 189 : from terminal xoff.
0000 190 : Save R3 prior to forking to create typeahead on read.
0000 191 :
0000 192 : V02-043 RKS0043 RICK SPITZ 11-FEB-1982
0000 193 : Zero fork byte in TWP to allow DMA of broadcast.
0000 194 : Prevent XON characteristic from being permantly set.
0000 195 :
0000 196 : V02-042 RKS0042 Rick Spitz 8-FEB-1982
0000 197 : Repair Alternate typeahead logic to allow setting
0000 198 : Permanent from users terminal.
0000 199 : Allocate typeahead buffer when starting read, if not already
0000 200 : done. This is needed for lines which are used for communications
0000 201 : on DMF-32 async lines.
0000 202 :
0000 203 : V02-041 ROW0066 Ralph D. Weber 31-JAN-1982
0000 204 : Enhance alternate class driver setup to relocate address in
0000 205 : alternate class driver vector table. Correct use of
0000 206 : unrelateable .ASCID directive.
0000 207 :
0000 208 : V02-040 RKS0040 RICK SPITZ 24-JAN-1982
0000 209 : USE INPUT VALUE FOR READ FIELD OFFSET.
0000 210 : ADD LOGIC TO BIND TO ALTERNATE DRIVER.
0000 211 :
0000 212 : V02-039 RKS0039 RICK SPITZ 15-DEC-1981
0000 213 : FIX MAINTENANCE DISPATCH LOGIC.
0000 214 : DISALLOW SETTING ALT TYPEAHEAD IF ONE ALREAY EXISTS.
0000 215 : REMOVE LOGIO REQUIREMENT FOR PARITY ENABLE.
0000 216 : FIX WRTSTARTIO RETURN ADDRESSING.
0000 217 : ALLOW NOECHO READ TO NOT BLOCK WRITES.
0000 218 : ADD WRITE POST ROUTINE TO REPLACE INSPOST LOGIC, THIS
0000 219 : CORRECTS RACE CONDITION IN HALF DUPLEX WRITE COMPLETIONS.
0000 220 : ADD SUPPORT FOR ALTERNATE CLASS DRIVER.
0000 221 :
0000 222 : V02-038 JLV0126 Jake VanNoy 1-Dec-1981
0000 223 : Add local echo logic and set speed privilege checking.
0000 224 :
0000 225 : V02-037 JLV0102 Jake VanNoy 27-Oct-1981
0000 226 : Changed TTYDEFS to \$TTYDEFS.
0000 227 :
0000 228 : V02-036 JLV0070 Jake VanNoy 28-Aug-1981

| | | | |
|------|-----|---|--|
| 0000 | 229 | : | Added UCB\$\$_TT_DEVDP1 checking and no refresh on broadcast. |
| 0000 | 230 | : | |
| 0000 | 231 | : | V02-035 RKS035 RICK SPITZ 26-AUG-1981 |
| 0000 | 232 | : | ADD MAINT ENABLE BIT |
| 0000 | 233 | : | |
| 0000 | 234 | : | V02-034 RKS034 RICK SPITZ 20-AUG-1981 |
| 0000 | 235 | : | ADD SUPPORT FOR ESCAPE MODIFIER ON READ. |
| 0000 | 236 | : | |
| 0000 | 237 | : | V02-033 RKS033 RICK SPITZ 12-AUG-1981 |
| 0000 | 238 | : | RESET DMA ABORT STATE IN WRITE DONE LOGIC. |
| 0000 | 239 | : | RESET CONTROLS STATE FOR MAINTENANCE FUNCTIONS. |
| 0000 | 240 | : | |
| 0000 | 241 | : | V02-032 RKS032 RICK SPITZ 27-JULY-1981 |
| 0000 | 242 | : | SEVERAL ENHANCEMENTS HAVE BEEN ADDED TO SUPPORT REVISIONS |
| 0000 | 243 | : | TO THE UCB STRUCTURE INCLUDING SPLIT SPEED, AND QUADWORD STATE |
| 0000 | 244 | : | AND DEVDEPEND FIELDS. |
| 0000 | 245 | : | SUPPORT FOR DIAGNOSTIC FUNCTIONS AND ENHANCED MODEM PROCESSING |
| 0000 | 246 | : | HAS BEEN ADDED. SEVERAL CHANGES TO SUPPORT THE CLASS/PORT |
| 0000 | 247 | : | STRUCTURE AS WELL AS ENHANCEMENTS TO ALLOW TERMINAL |
| 0000 | 248 | : | INITIATED CONTROL S AND Q DURING BROADCAST HAVE ALSO BEEN |
| 0000 | 249 | : | ADDED. |
| 0000 | 250 | : | |
| 0000 | 251 | : | V02-031 RKS031 RICK SPITZ 26-FEB-1981 |
| 0000 | 252 | : | REMOVE V2.0 AUDIT TRAILS |
| 0000 | 253 | : | |


```

0000 255      .SBTTL Declarations
0000 256
0000 257      :
0000 258      : EXTERNAL SYMBOLS
0000 259      :
0000 260      $ARBDEF      : DEFINE ACCESS RIGHTS BLOCK
0000 261      $CADEF      : DEFINE CONDITIONAL ASSEMBLY PARAMETERS.
0000 262      $CRBDEF      : DEFINE CRB
0000 263      $DPTDEF      : DEFINE DPT OFFSETS
0000 264      $IODEF      : DEFINE I/O FUNCTION CODES
0000 265      $IPLDEF      : DEFINE IPL'S
0000 266      $IRPDEF      : DEFINE IRP
0000 267      $PRDEF      : DEFINE PROCESSOR REGISTERS
0000 268      $PRVDEF      : DEFINE PRIVILEGE MASK BITS
0000 269      $SSDEF      : Define system status codes
0000 270      $TTDEF      : DEFINE TERMINAL CHARACTERISTICS
0000 271      $TT2DEF      : DEFINE TERMINAL CHARACTERISTICS
0000 272      $TTYDEF      : DEFINE TERMINAL DRIVER SYMBOLS
0000 273      $UCBDEF      : DEFINE UCB
0000 274      $VECDEF      : DEFINE CRB VECTOR OFFSETS
0000 275      $TTYMACS      : DEFINE TERMINAL MACROS
0000 276      $TTYDEFS      : DEFINE TERMINAL DEFINITIONS
0000 277      $TTYMODEM      : DEFINE TERMINAL MODEM DEFINITIONS
0000 278
00000000 279      .PSECT $$$115_DRIVER, LONG      : DEFINE NON-PAGED PSECT

```

```
0000 281 .SBTTL TTY$STARTIO - START I/O OPERATION ON TERMINAL
0000 282 :++
0000 283 : TTY$STARTIO - START I/O OPERATION ON TERMINAL
0000 284 :
0000 285 : FUNCTIONAL DESCRIPTION:
0000 286 :
0000 287 : THIS ROUTINE IS ENTERED WHEN THE UNIT IS IDLE AND THERE IS A PACKET TO PROCESS.
0000 288 :
0000 289 : INPUTS:
0000 290 :
0000 291 : I/O PACKET FORMATTED AS DESCRIBED IN TTYFDT.
0000 292 :
0000 293 : R3 = I/O PACKET ADDRESS
0000 294 : R5 = LOGICAL UCB ADDRESS
0000 295 :
0000 296 : OUTPUTS:
0000 297 :
0000 298 : NONE
0000 299 :--
0000 300 TTY$STARTIO:: ; START TERMINAL I/O
0000 301 :
0000 302 : MOVE TO PHYSICAL UCB CONTEXT. THIS INVOLVES DUPLICATING
0000 303 : MANIPULATIONS TO THE LOGICAL UCB DONE BY IOCSINITIATE
0000 304 :
0000 305 MOVL UCBSL_TL_PHYUCB(R5),R0 ; GET PHYSICAL UCB ADDRESS
0000 306 MOVL R3,UCBSL_IRP(R0) ; COPY IRP ADDRESS TO PHYS UCB
0000 307 MOVQ IRPSL_SVAPTE(R3),UCBSL_SVAPTE(R0)
0000 308 BICW #UCBSM_CANCEL!UCBSM_TIMEOUT,UCBSW_STS(R0)
0000 309 MOVL R0,R5 ; SWITCH TO PHYSICAL UCB
0000 310
0000 311 BSBW TTY$LOCK ; SETUP IPL AND REGISTERS
0000 312 BICW3 #^C<IOSM_FCODE>,IRPSW_FUNC(R3),R4 ; GET INTERNAL FUNCTION CODE
0000 313 CASE R4,TYPE=B,<DO_READ,DO_WRITE,DO_SETM,DO_SETC,DO_HANGUP,-
0000 314 DO_MAINT,DO_HANGUP,DO_CONNECT,DO_DISCONNECT>
0037 315
```

50 00A0 C5 D0 0000 305
58 A0 53 D0 0005 306
78 A0 2C A3 7D 0009 307
64 A0 0048 8F AA 000E 308
55 50 D0 0014 309
0017 310
FFE6' 30 0017 311
54 20 A3 FFC0 8F AB 001A 312
0021 313
0021 314
0037 315

```
0037 317 .sbttl START_ID ACTION ROUTINES
0037 318
0037 319 ;
0037 320 ; CONNECT THIS PUCB TO A DETACHED LUCB
0037 321 DO_CONNECT:
0037 322 BBC #IOSV TT DISCON, -
0039 323 IRPSW_FUNC(R3), 10$ ; SKIP UNLESS DISCONNECT SPECIFIED
003C 324 BICL #TT2SM_DISCONNECT,UCBSL_DEVDEPND2(R5); FORCE HANGUP TO COMMAND PROCE
0044 325 10$:
0044 326 MOVL UCBSL_PDT(R5),R1 ; GET TARGET LUCB ADDRESS
0049 327 BEQL 25$ ; NONE, MUST BE JUST DELETED
004B 328
004B 329 SET_STATE RECONNECT ; SET RECONNECT STATE TO TARGET LUCB
004F 330
004F 331 PUSHR #^M<R1,R3> ; SAVE IRP ADDRESS AND LUCB
0051 332 MOVL #TTYSV_FD_DISCONNECT,R4 ; SCHEDULE DISCONNECT COMMAND PUCB
0054 333 BSBW TTYSV_FORK
0057 334 POPR #^M<R1,R3> ; SAVE IRP ADDRESS AND LUCB
0059 335
0059 336 :
0059 337 :
0059 338 :
0059 339 MOVQ UCBSL_DEVDEPEND(R1),IRPSQ_TT_STATE(R3)
005E 340 MOVQ UCBSL_DEVTYPE(R1),IRPSL_MEDIA+1(R3) ; TERMINAL TYPE
0063 341 MOVW UCBSL_DEVBUFSIZ(R1),IRPSL_MEDIA+2(R3) ; WIDTH
0068 342 CLRL IRPSV_TT_PRMT(R3)
006B 343 CLRL IRPSL_VAL5(R3)
006F 344
006F 345 BICL #TTSM_MODEM,IRPSQ_TT_STATE(R3) ; TRACK MODEM TO BE SAME AS
0077 346 BBC #TTSV_MODEM,UCBSL_DEVDEPEND(R5),20$ ;
007C 347 BISL #TTSM_MODEM,IRPSQ_TT_STATE(R3) ;
0084 348 20$:
0084 349 BICL #TT2SM_DISCONNECT,IRPSQ_TT_STATE+4(R3) ; TRACK DISCONNECT TO BE SAM
008C 350 BBC #TT2SV_DISCONNECT,UCBSL_DEVDEPND2(R5),22$ ;
0091 351 BISL #TT2SM_DISCONNECT,IRPSQ_TT_STATE+4(R3) ;
0099 352 22$:
0099 353
0099 354
0099 355 BRW DO_SET ; NOW INVOKE SET MODE ACTION ROUTINE
009C 356
009C 357 25$:
009C 357 MOVZWL #SS$ NOSUCHDEV,R0 ; INDICATE DEVICE NOT AVAILABLE
00A1 358 BRW TTYSDONE
```


| | | | | | | |
|----|------|------|------|-----|----------------|---|
| | | | 00A4 | 360 | | |
| | | | 00A4 | 361 | | |
| | | | 00A4 | 362 | : | DISCONNECT COMMAND LUCB FROM PUCB. |
| | | | 00A4 | 363 | : | IF NOT DETACHED, HANGUP SIGNALLED TO COMMAND PROCESS |
| | | | 00A4 | 364 | | |
| | | | 00A4 | 365 | DO_DISCONNECT: | |
| 54 | 53 | DD | 00A4 | 366 | PUSHL | R3 : SAVE IRP |
| | 02 | DD | 00A6 | 367 | MOVL | #TTY\$V_FD_DISCONNECT,R4 : SCHEDULE DISCONNECT ON THAT PUCB |
| | FF54 | 30 | 00A9 | 368 | BSBW | TTY\$CRE_FORK |
| | 53 | BEDD | 00AC | 369 | POPL | R3 : RESTORE IRP |
| 50 | 01 | 3C | 00AF | 370 | MOVZWL | #SS\$ NORMAL,R0 |
| | 0680 | 31 | 00B2 | 371 | BRW | TTY\$DONE |

```

00B5 373
00B5 374
00B5 375 ; PROCESS HANGUP FUNCTION. THIS ROUTINE FORCES A MODEM HANGUP
00B5 376
00B5 377 DO_HANGUP:
38 BB 00B5 378 PUSHR #*M<R3,R4,R5> ; SAVE REGISTERS
FF46' 30 00B7 379 BSBW CLASS MODEM DIS ; DISCONNECT UNIT
38 BA 00BA 380 POPR #*M<R3,R4,R5> ; RESTORE REGISTERS
0363 51 00BC 381 BRW DO_EXIT
00BF 382

```

```
00BF 384
00BF 385 ; PROCESS MAINTENANCE FUNCTIONS
00BF 386
00BF 387 DO_MAINT:
41 44 A5 E0 00BF 388 BBS #TTSV_MODEM,- ; DISALLOW IF MODEM LINE
54 0118 C5 D0 00C1 389 UCBSL_DEVDEPEND(R5),30$
04 EG 00C4 390 MOVL UCBSL_TT_PORT(R5),R4 ; ACCESS PORT VECTOR
24 20 A3 EG 00C9 391 BBS #IOSV_SET_MODEM,- ; BRANCH IF SET MODEM FUNCTION
06 07 EF 00CB 392 IRPSW_FUNC(R3),20$
50 20 A3 00D1 393 EXTZV #IOSV_LOOP,#<IOSV_LOOP_EXT-IOSV_LOOP+1>,-
012A C5 50 88 00D4 394 IRPSW_FUNC(R3),R0 ; GET MAINT SUBMODIFIERS
50 50 D4 00D9 395 BISB R0,UCBSB_TT_MAINT(R5) ; PASS TO PORT
FF 22 30 00DB 396 CLRL R0 ; ASSUME ERROR, FOR NULL POST ROUTIN
7F 8F 8A 00DE 397 BSBW TTYSMAINT ; INVOKE PORT DRIVER TO DO FUNCTION
012A C5 00E1 398 BICB #^C<UCBSM_TT_DSBL>,- ; RESET ALL BUT DISABLE
1E 50 E9 00E4 400 UCBSB_TT_MAINT(R5)
50 0118 C5 D0 00E7 401 BLBC R0,30$ ; FAILURE
FF 11 30 00EC 402 MOVL UCBSL_TT_PORT(R5),R0 ; GET PORT VECTOR ADDRESS
0330 31 00EF 403 BSBW TTYSRESUME ; RESET ANY CONTROLS STATE
52 3A A3 3C 00F2 404 20$: BRW DO_EXIT ; SUCCESS
52 E5 BF 8A 00F6 405 MOVZWL IRPSL_MEDIA+2(R3),R2 ; PROCESS SET MODEM SIGNALS
00FA 406 BICB #^C<TTSM_DS_DTR!- ; GET SET/RESET MODEM MASK
00FA 407 TTSM_DS_SECTX!- ; CLEAR ALL BUT MODEM OUTPUT
00FA 408 TTSM_DS_RTS>,R2 ; BITS
53 DD 00FA 409 PUSHL R3 ; SAVE VOLITAL REGISTER
FF 01 30 00FC 410 BSBW TTYSDS_SET ; SET /RESET SPECIFIED SIGNALS
53 8ED0 00FF 411 POPL R3 ; RESTORE REGISTER
031D 31 0102 412 BRW DO_EXIT ; SUCCESS EXIT
50 2C 3C 0105 413 30$: MOVZWL #SS$ _ABORT,R0 ; ERROR EXIT
51 D4 0108 414 CLRL R1
0628 31 010A 415 BRW TTYS$DONE
010A 416
```



```
0100 418 :  
0100 419 : READ OPERATION  
0100 420 :  
0100 421 DO_READ:  
54 78 A5 D0 0100 422 MOVL UCB$$_SVAPTE(R5),R4 : GET THE ADDRESS OF THE READ PACKET  
04 62 40 A3 C8 0111 423 :  
04 A2 44 A3 C8 0115 424 BISL IRP$$_TT_STATE(R3), (R2) : Set the read state bits.  
38 A3 D4 011A 425 BISL IRP$$_TT_STATE+4(R3), 4(R2)  
04 04 AA 011D 426 :  
68 A5 011F 427 CLRL IRP$$_MEDIA(R3) : Set up storage for the read  
03 20 A3 0121 428 : terminator.  
FED7' 30 0121 429 BICW #UCB$$_TT_NOTIF, - : Set the 'user has not been  
0123 430 UCB$$_DEVSTS(R5) : notified' bit.  
0126 431 BBC #IOSV_PURGE, - : Branch forward if purge type-  
0129 432 IRP$$_FUNC(R3), 10$ : ahead not requested.  
0129 433 BSBW TTY$$_PURGE_AHEAD : Otherwise, purge buffer.  
0129 434 : the write completes.  
00E4 C5 D5 0129 435 10$: TSTL UCB$$_TT_TYPAHD(R5) : Type ahead buffer allocated?  
73 13 012D 436 BEQL 30$ : Not yet  
FECE' 30 012F 437 :  
0132 438 12$: BSBW TTY$$_SETUP_READ : Set up the UCB for a read  
0132 439 : operation.  
0132 440 :  
0132 441 : CHECK FOR LINE FEED NEEDED  
0132 442 :  
0132 443 :  
0132 444 :  
0132 445 :  
0132 446 IF STATE - : Skip if passall, or  
0132 447 <PASALL>, 25$ :  
0136 448 IF NOT STATE NOECHO, 14$ : NO ECHO THEN  
013A 449 CLR STATE EDITING : NO EDITING  
013E 450 14$: IF STATE - :  
013E 451 <NC, WRAP>, 20$ : if already did line feed.  
0145 452 :  
0145 453 IF NOT STATE NOECHO, 15$ : Branch if echo  
26 48 A5 E1 0149 454 BBC #TTY$$_V_LOCALECHO, - : Branch if not local echo  
014B 455 UCB$$_DEVDEPND2(R5), 20$ :  
014E 456 :  
00FC C5 B5 014E 457 15$: TSTW UCB$$_TT_CURSOR(R5) : CURSOR AT 0?  
20 12 0152 458 BNEQ 20$ : If no, send no line feed.  
00FF C5 91 0154 459 CMPB UCB$$_TT_LASTC(R5), - : Was the last character also a  
0D 0158 460 #TTY$$_CR : carriage return?  
19 12 0159 461 BNEQ 20$ : No. Don't send free linefeed.  
OF 0122 C5 07 E0 015B 462 IF NOT STATE SKIPLF, 17$ : NO SKIP LINEFEED THEN BYPASS NOCRLF CHECK  
015F 463 BBS #TTY$$_V_PC_NOCRLF, UCB$$_TT_PRTCTL(R5), 20$ : SO JUST ECHO THE CHARACTER  
0165 464 17$: SET STATE <SENDF$ : SEND A LINE FEED FIRST  
0168 465 CLR STATE <SKIPLF> :  
016C 466 IF NOT STATE PROMPT, 20$ : DO WE HAVE A  
0170 467 SET STATE <SKIPLF> : SEND A LINE FEED FIRST  
0174 468 20$: IF STATE RDVERIFY, 25$ : THIS ISN'T NECESSARY IF READ VERIFY  
0178 469 :  
54 78 A5 D0 0178 470 MOVL UCB$$_SVAPTE(R5), R4 : GET THE READ PACKET ADDRESS  
7E 00FC C5 3C 017C 471 MOVZWL UCB$$_TT_CURSOR(R5), -(SP) : SAVE THE CURSOR POSITION FOR ECHOING  
02 44 A4 B1 0181 472 CMPW TTY$$_RB_MODE(R4), #TTY$$_ER_ECHLINE : IS THIS A READ WITH INITIAL  
0185 473 : OFFSET.  
0D 12 0185 474 BNEQ 21$ : NO THEN USE NORMAL
```

```

- Terminal driver start/stop I/O routine 16-SEP-1984 02:18:30 VAX/VMS Macro v04-00 Page 13
START_IO ACTION ROUTINES 5-SEP-1984 04:17:09 [TTDRVR.SRC]TTYSTRSTP.MAR:1 (11)

```

| | | | | | | | | | |
|------|----|------|------|------|------|-------|--------|--|---|
| 00FC | C5 | 012B | C5 | 9B | 0187 | 475 | MOVZBW | UCBSB_TT_OLDCPZORG(R5),UCBSW_TT_CURSOR(R5); | YES THEN USE THE |
| | | | | | 018E | 476 | | | : STORED INITIAL CURSOR POSITION |
| 3A | A4 | 012B | C5 | 9B | 018E | 477 | MOVZBW | UCBSB_TT_OLDCPZORG(R5),TTY\$W_RB_CPZORG(R4); | |
| | | 32 | A4 | B4 | 0194 | 478 | CLRW | TTY\$W_RB_LINREST(R4) | : NO-EXTRA CHARACTERS |
| | | FE66 | | 30 | 0197 | 479 | BSBW | FIND BOL-NOCLEAR | : find the wrapping and |
| 00FC | C5 | 8E | F7 | 019A | 480 | | RVTLW | (SP)+UCBSW_TT_CURSOR(R5); | RESTORE THE CURSOR POSITION FOR ECHOING |
| | | 0390 | 31 | 019F | 481 | 25\$: | BRW | TTY\$STARTOUTPUT | : Go start the read. |
| | | | | | 01A2 | 482 | | | |
| | | | | | 01A2 | 483 | | | |
| | | | | | 01A2 | 484 | | | |
| | | 53 | DD | 01A2 | 485 | | PUSHL | R3 | : SAVE IRP ADDRESS |
| | | 53 | D4 | 01A4 | 486 | | CLRL | R3 | : INDICATE NO DATA |
| 54 | | 01 | D0 | 01A6 | 487 | | MOVL | #TTY\$V_FD_GETAHD,R4 | : ASK FOR TYPEAHD FORK |
| | | FE54 | | 30 | 01A9 | 488 | BSBW | TTY\$CRE_FORK | : GO ALLOCATE BUFFER |
| | | 53 | 8ED0 | 01AC | 489 | | POPL | R3 | : RESTORE IRP ADDRESS |
| | | FF7D | 31 | 01AF | 490 | | BRW | 12\$ | : CONTINUE PROCESSING |
| | | | | | 01B2 | 491 | | | |

```
01B2 493
01B2 494 ; SET MODE OPERATION -
01B2 495
01B2 496 DO_SETM: BRW DO_SET
01B2 497
01B5 498
01B5 499 ; DO SET CHARACTERISTICS
01B5 500
01B5 501 DO_SETC: ; DO PRIVILEGED SET
01B5 502 CMPW #12,IRPSW_BCNT(R3) ; CHECK PARAMETERS
01B5 503 DO_SET ; ALL SPECIFIED
00C8 06 15 01B9 504 BLEQ UCB$$_TT_DECHA1(R5),- ; INIT DEFAULT IF NOT SPECIFIED
44 A3 40 01BB 505 MOVL IRPSQ_TT_STATE+4(R3)
01C1 506
01C1 507 ; PROCESS CHANGE OF CHARACTERISTICS AND MODE
01C1 508 ; CHANGE BASIC MODE BITS IN UCB$$_DEVDEPEND
01C1 509
01C1 510 DO_SET:
54 44 A5 40 A3 CD 01C1 511 XORL3 IRPSQ_TT_STATE(R3),UCB$$_DEVDEPEND(R5),R4; GET MODIFIED BITS
08 54 0D E5 01C7 512 BBCC #TT$V_REMOTE,R4,8$ ; DISALLOW CLEARING REMOTE BIT
40 A3 00002000 8F CA 01CB 513 BICL #TT$M_REMOTE,IRPSQ_TT_STATE(R3)
01D3 514 ; DISALLOW SETTING REMOTE BIT
01D3 515 BS:
44 A5 54 CA 01D3 516 BICL R4,UCB$$_DEVDEPEND(R5) ; CLEAR THE CHANGED BITS
44 A5 40 A3 C8 01D7 517 BISL IRPSQ_TT_STATE(R3),UCB$$_DEVDEPEND(R5);
41 A5 39 A3 90 01DC 518 MOVB IRPSL_MEDIA+1(R3),UCB$$_DEVTYPE(R5); INSERT NEW TERMINAL TYPE
01E1 519
01E1 520 DEVDP1 BIT CHECKING
01E1 521
01E1 522 MOVL IRPSQ_TT_STATE+4(R3),R0 ; GET SECOND DEVDEPEND WORD
51 48 A5 50 CD 01E5 523 XORL3 R0,UCB$$_DEVDEPND2(R5),R1 ; GET MODIFIED BITS
50 00000200 8F CA 01EA 524 BICL #<TT2$M_DCL_MAILBX>,R0 ; REMOVE DCL SPECIFIC BITS
01F1 525
01F1 526 BBC #TT2$V_DMA,R1,12$ ; SKIP IF DMA NOT CHANGED
14 50 06 E1 01F5 527 BBC #TT2$V_DMA,R0,10$ ; BRANCH IF TURNING DMA OFF
0E 0122 C5 02 E1 01F9 528 BBC #TTY$V_PC_DMAAVL,UCB$$_TT_PRTCTL(R5),10$ ; DONT IF FEATURE NOT AVAIL
50 00000040 8F C8 01FF 529 BISL #TT2$M_DMA,R0 ; SET DMA CHARACTERISTIC ON
0122 C5 02 AB 0206 530 BISW #TTY$M_PC_DMAENA,UCB$$_TT_PRTCTL(R5) ; ENABLE IN PORT
0C 11 020B 531 BRB 12$
50 0122 C5 02 AA 020D 532 10$: BICW #TTY$M_PC_DMAENA,UCB$$_TT_PRTCTL(R5) ; DISABLE DMA IN PORT
50 00000040 8F CA 0212 533 BICL #TT2$M_DMA,R0 ; RESET DMA CHARACTERISTIC
0219 534
0219 535 12$: NOMOD ALTYPEAHD ; DISALLOW CHANGING TYPE AHEAD
0224 536
0224 537 BBS #TT2$V_MODHANGUP,-
11 48 A5 E0 0226 538 UCB$$_DEVDEPND2(R5),15$ ; BRANCH IF MODIFY HANGUP ALLOWED
0229 539
0229 540 15$: PRIV_TO_MOD HANGUP ; REQUIRE PRIV TO MODIFY HANGUP
023A 541 PRIV_TO_MOD SETSPEED ; REQUIRE PRIV TO MODIFY SET SPEED
024B 542 PRIV_TO_MOD SECURE ; REQUIRE PRIVS TO MODIFY SECURE SERVER
025C 543 PRIV_TO_MOD MODHANGUP ; REQUIRE PRIV TO MODIFY MODHANGUP
026D 544
06 50 05 E1 026D 545 BBC #TT2$V_XON,R0,20$ ; BRANCH IF NO XON REQUESTED
50 20 CA 0271 546 BICL #TT2$M_XON,R0 ; RESET XON BIT.
FD89 30 0274 547 BSBW TTY$RESUME ; CALL RESUME
0277 548
0277 549 20$:
```



```

      4B A5 50 D0 0277 550      MOVL    R0,UCBSL_DEVDEPND2(R5) ; SET SECOND DEVDEPENDENT WORD
      0278 551
      0278 552      SET UP WIDTH
      0278 553
      42 A5 3A A3 B0 0278 554      MOVW    IRPSL_MEDIA+2(R3),UCBSW_DEVBUFSIZ(R5); INSERT NEW CARRIAGE WIDTH
      0280 555
      0280 556      SET UP SPEED
      0280 557
      51 4C A3 3C 0280 558      MOVZWL  IRPSW_TT_PRMPRT(R3),R1 ; GET NEW SPEED
      1E 13 0284 559      BEQL     30$ ; IF EQL THEN NO CHANGE
      0286 560
      0286 561      SET SPEED PRIVILEGE CHECK
      0286 562
      00F4 C5 51 91 0286 563      CMPB    R1,UCBSW_TT_SPEED(R5) ; IS LOW ORDER BYTE OF SPEED CHANGING?
      12 13 0288 564      BEQL     28$ ; BRANCH IF NOT
      028D 565
      08 E1 028D 566      BBC      #TT2$V SETSPEED,-
      0D 48 A5 028F 567      UCB$S DEVDEPND2(R5),28$ ; BRANCH IF SET SPEED ALLOWED
      5B B3 00400080 8F D3 0292 568      BITL     #<<1$PRV$V LOG IO>>! - ; DOES PROCESS HAVE LOG_IO
      029A 569      <1$PRV$V PRV IO>>,- ; OR PHY IO PRIVILEGE?
      029A 570      @IRPSL_ARB(R3) ; CHECK ACCESS RIGHTS BLOCK
      03 12 029A 571      BNEQ     28$ ; BRANCH IF PRIVILEGED
      019D 31 029C 572      BRW      NOPRIV_EXIT ; PRIV FAILURE
      029F 573
      029F 574
      029F 575      PROCESS PARITY SETTINGS
      029F 576
      00F4 C5 51 B0 029F 577 28$: MOVW    R1,UCBSW_TT_SPEED(R5) ; INSERT LINE SPEED
      12 009C C3 05 E1 02A4 578 30$: BBC      #TT$V_ALTRPAR,IRPSL_VAL5(R3),35$; BR IF PARITY SHOULD NOT BE ALTERED
      50 009C C3 3F 8F 8B 02AA 579      BICB3   #^C<TT$M PARITY!TT$M ODD>,IRPSL_VAL5(R3),R0; RESET BITS
      00F8 C5 C0 8F 8A 02B1 580      BICB     #TT$M PARITY!TT$M ODD,UCBSB_TT_PARITY(R5); CLEAR CURRENT PARITY
      00F8 C5 50 8B 02B7 581      BISB     R0,UCBSB_TT_PARITY(R5) ; INSERT NEW VALUE
      02BC 582
      02BC 583      SET UP CHARACTER SIZE AND STOP BITS
      02BC 584
      02BC 585 35$:
      08 009C C3 04 E0 02BC 586      BBS      #TT$V_ALTFRAME,IRPSL_VAL5(R3),36$; DOES THE USER WANT A NEW FRPAM SI
      21 00F8 C5 02 E1 02C2 587      BBC      #UCBSV_TT_USERFRAME,UCBSB_TT_PARITY(R5),37$; DID THE USER SPECIFY
      02C8 588      ; THE FRAME SIZE?
      00 00F8 C5 3B 11 02C8 589      BRB      42$ ; YES THEN DON'T BOTHER IT
      50 009C C3 FFFFFFFF0 8F CB 02CA 590 36$: BBCC    #UCBSV_TT_USERFRAME,UCBSB_TT_PARITY(R5),38$
      00F8 C5 02 03 50 F0 02DA 591 38$: BICL3   #^C<^XOF>,IRPSL_VAL5(R3),R0; GET THE NEW FRAME SIZE
      1C 00F8 C5 02 E3 02DC 592      BEQL     37$ ; 0 SPECIFIED THEN CLEAR USER FRAME
      02E3 593      INSV     R0,#UCBSV_TT_LEN,#2,UCBSB_TT_PARITY(R5); SET THE
      02E9 594      ; PARITY CORRECTLY
      11 00F8 C5 06 E1 02E9 595      BBBS     #UCBSV_TT_USERFRAME,UCBSB_TT_PARITY(R5),42$; AND SETUSER FRAME
      0F E0 02EF 596      ; SPECIFIED THEN CONTINUE ON
      0C 44 A5 02F1 600      BBC      #TT$V_PARITY,-
      00F8 C5 18 8A 02F4 601      UCB$S_TT_PARITY(R5),40$ ; IF NO PARITY, USE 8 BIT
      00F8 C5 10 8B 02F9 602      BBS      #TT$V_EIGHTBIT,-
      05 11 02FE 603      UCB$S_DEVDEPND(R5),40$ ; USE 8 BIT SIZE
      00F8 C5 18 8B 0300 604 40$: BICB     #UCBSM_TT_LEN,UCBSB_TT_PARITY(R5) ; RESET CHARACTER FRAME
      0305 605      BISB     #^X10,UCBSB_TT_PARITY(R5) ; SET 7 BIT CHARACTER FRAME
      0305 606 42$: BRB      42$
```

```
11 009C C3 0A E1 0305 607 BBC #TT$V_ALTDISPAR,IRP$L_VAL5(R3),41$ : CHECK FOR DISABLE PARITY E
00F8 C5 02 CA 030B 608 BICL #UCB$M_TT_DISPARERR,UCB$B_TT_PARITY(R5) : CLEAR DISMISS
06 009C C3 09 E1 0310 609 BBC #TT$V_DISPARERR,IRP$L_VAL5(R3),41$ : DOES HE WANT IT SET
00 00F8 C5 01 E2 0316 610 BBS #UCB$V_TT_DISPARERR,UCB$B_TT_PARITY(R5),41$ : YES THEN SET IT
07 009C C3 08 E0 031C 611 41$: BBS #TT$V_TWOSTOP,IRP$L_VAL5(R3),43$ : DOES HE WANT TWO STOP BITS
04 00F4 C5 07 91 0322 612 CMPB UCB$W_TT_SPEED(R5),#4 : SPEED <= 150 BAUD?
00F8 C5 20 88 0329 613 BGTR 44$ : NO
05 11 032E 614 43$: BISB #UCB$M_TT_STOP,UCB$B_TT_PARITY(R5) : FLAG 2 STOP BITS
05 11 032E 615 BRB 46$
00F8 C5 20 8A 0330 616 44$: BICB #UCB$M_TT_STOP,UCB$B_TT_PARITY(R5) : FLAG 1 STOP BIT
0335 617
0335 618 : PROCESS FILL DATA
0335 619
0335 620
0335 621 46$:
CA 44 A5 50 D4 0335 622 CLRL R0 : ASSUME NEW VALUE IS 0
50 4E A3 9A 0337 623 BBC #TT$V_CRFILL,UCB$L_DEVDEPEND(R5),50$: CR FILL ON?
02 54 0A E0 033C 624 MOVZBL IRP$W_TT_PRMT+2(R3),R0 : GET NEW VALUE
00F6 C5 0C 13 0344 625 BBS #TT$V_CRFILL,R4,50$ : CHANGE?
05 90 0346 626 BEQL 60$ : IF NEQ EQL 0 THEN NO CHANGE
00 44 A5 0A E5 034B 627 50$: MOVB R0,UCB$B_TT_CRFILL(R5) : RESET VALUE
05 12 0348 628 BNEQ 60$ : IF NEQ THEN OK
0A 44 A5 0A E5 034D 629 BBCC #TT$V_CRFILL,UCB$L_DEVDEPEND(R5),60$: SET OFF
50 D4 0352 630 60$: CLRL R0 : ASSUME NEW VALUE IS 0
0A 44 A5 0B E1 0354 631 BBC #TT$V_LFFILL,UCB$L_DEVDEPEND(R5),65$: LF FILL ON?
50 4F A3 9A 0359 632 MOVZBL IRP$W_TT_PRMT+3(R3),R0 : GET NEW VALUE
02 54 0B E0 035D 633 BBS #TT$V_LFFILL,R4,65$ : CHANGE?
00F7 C5 0C 13 0361 634 BEQL 75$ : IF NEQ EQL 0 THEN NO CHANGE
05 90 0363 635 65$: MOVB R0,UCB$B_TT_LFFILL(R5) : RESET VALUE
00 44 A5 0A E5 0368 636 BNEQ 75$ : IF NEQ THEN OK
05 12 036A 637 BBCC #TT$V_LFFILL,UCB$L_DEVDEPEND(R5),75$: SET OFF
036F 638
036F 639 : CHECK FOR CHANGE IN STATUS OF MODEM
036F 640
036F 641 75$:
12 54 15 E1 036F 642 BBC #TT$V_MODEM,R4,80$ : NO CHANGE IN MODEM STATUS
1F BB 0373 643 PUSHR #^M<R0,R1,R2,R3,R4> : SAVE VOLITAL REGISTERS
51 00 9A 0375 644 MOVZBL #MODEM$C_INIT,R1 : ASSUME MODEM INIT
44 A5 15 E0 0378 645 BBS #TT$V_MODEM,UCB$L_DEVDEPEND(R5),- : IT IS INIT
03 037C 646 77$: MOVZBL #MODEM$C_SHUTDOWN,R1 : NO, SHUT DOWN
51 01 9A 037D 647 77$:
FC7D' 30 0380 648 77$: BSBW TRANSITION NOCHECK : DECLARE MODEM TRANSITION
1F BA 0383 649 POPR #^M<R0,R1,R2,R3,R4>
0385 650
0385 651 80$:
0385 652
0385 653 : enable or disable AUTO XON AND XOFF
0385 654
0385 655
0122 C5 0040 8F A8 0385 656 BISW #TTY$M_PC_XOFENA,UCB$W_TT_PRTCTL(R5); TURN ON AUTO XOFF
05 44 A5 00 E0 038C 657 BBS #TT$V_PASSALL,UCB$L_DEVDEPEND(R5),84$: IS THIS PASSALL? YES THEN
07 44 A5 05 E0 0391 658 BBS #TT$V_TTSYNC,UCB$L_DEVDEPEND(R5),85$: IF TT SYNC IS SET THEN LEAVE I
0122 C5 0040 8F AA 0396 659 84$: BICW #TTY$M_PC_XOFENA,UCB$W_TT_PRTCTL(R5); TURN OFF AUTO XOFF
039D 660 85$:
039D 661
039D 662 : COPY OVER PASSALL AND NOECHO TO CURRENT STATE
039D 663
```

```

      54 44 A5 FC 8F BB 039D 664 BICB3 #^C<TTSM PASSALL!TTSM NOECHO>,UCBSL_DEVDEPEND(R5),R4
04 A2 02 02 54 FO 03A3 665 INSV R4,TTY$V ST_PASALL,#2,4(R2); INSERT IN STATE VECTOR
      54 44 A5 01 03 EE 03A9 666 EXTIV #TT$V_ESCAPE,#1,UCBSL_DEVDEPEND(R5),R4 ; GET CURRENT SETTING
04 A2 01 0B 54 FO 03AF 667 INSV R4,TTY$V ST_ESCAPE,#T,4(R2) ; UPDATE IN STATE
      04 48 A5 12 E1 03B5 668 BBC #TT2$V_PASTHRU,UCBSL_DEVDEPN2(R5),98$ ; IN PASS THRU MODE
      03BA 669 SET_STATE PASACL
      03BE 670 98$:
      03BE 671 ;
      03BE 672 ; INIT THE UNIT TO CHANGE THE SPEED AND PARITY
      03BE 673 ;
      FC3F' 30 03BE 674 BSBW TTY$SET_LINE ; INIT LINE SPEED AND PARITY
      03C1 675 ;
      03C1 676 ; IF MULTI IS SET THEN THE I/O MUST BE STARTED
      03C1 677 ;
      016A 30 03C1 678 100$: IF NOT_STATE MULTI,110$ ; BR IF MULTI NO SET
      03C5 679 BSBW TTY$STARTOUTPUT ; START THE MULTIPLE OUTPUT
      03C8 680 ;
      03C8 681 ; CHECK FOR SET CHARACTERISTICS AND RETURN IOSB DATA
      03C8 682 ;
      03C8 683 110$: MOVL UCBSL_IRP(R5),R3 ; GET CURRENT PACKET ADDRESS
03 20 A3 53 58 A5 DO 03CC 684 CMPZV #IRP$V_FCODE,#IRP$S_FCODE,IRP$W_FUNC(R3),#TTY$C_FC_SETC; SET CHAR?
      00E8 C5 00F4 C5 DO 03D2 685 BNEQ 120$ ; IF NEQ THEN NO
      01 01 E1 03D4 686 MOVL UCBSW TT_SPEED(R5),UCBSW_TT_DESPEE(R5); RESET PERM SPEED
      05 48 A5 03DB 687 BBC #TT2$V_AUTOBAUD,-
      00E8 C5 00F8 C5 03DD 688 UCBSL_DEVDEPN2(R5),115$ ; BRANCH IF NOAUTOBAUD
      00EC C5 00F0 C5 41 A5 DO 03E0 689 MOVZBW #TT$C_BAUD_9600,-
      00C4 C5 44 A5 00002000 8F CB 03E2 690 UCBSW_TT_DESPEE(R5) ; SET PERMANENT 9600 BAUD FOR AUTOBAUD
      00C8 C5 48 A5 DO 03E5 691 115$: MOVW UCBSB_TT_PARITY(R5),UCBSB_TT_DEPARI(R5); RESET PERM PARITY
      06 44 A3 07 E1 0403 692 MOVL UCBSB_DEVTYPE(R5),UCBSB_TT_DETYPE(R5); RESET TYPE AND WIDTH
      00 00C8 C5 07 E2 0408 693 BICL3 #TTSM_REMOTE,UCBSL_DEVDEPEND(R5),UCBSL_TT_DECHAR(R5); RESET PERM CHA
      040E 694 MOVL UCBSL_DEVDEPN2(R5),UCBSL_TT_DECHA1(R5); UPDATE SECOND CHAR WORD
      040E 695
      040E 696 BBC #TT2$V_ALTTYPEAND,IRP$Q_TT_STATE+4(R3),120$; SKIP IF ALTERNATE
      040E 697 BBSS #TT2$V_ALTTYPEAND,UCBSL_TT_DECHA1(R5),120$ ; TYPEAHEAD NOT SPECIFIED
      040E 698 ; ONLY ALLOW SETTING
      040E 699 ; AS PERM CHARACTERISTIC
      040E 700 120$:
      040E 701 ;
      040E 702 ; UPDATE NEWLY WRITTEN FIELDS WHICH ARE MAINTAINED
      040E 703 ; IN BOTH THE LOGICAL ANY PHYSICAL UCB
      040E 704 ;
      50 00C0 C5 DO 040E 705 MOVL UCBSL_TT_LOGUCB(R5),R0 ; GET LOGICAL UCB ADDRESS
      44 A0 44 A5 DO 0413 706 MOVL UCBSL_DEVDEPEND(R5),UCBSL_DEVDEPEND(R0) ; UPDATE CHARACTERISTICS
      48 A0 48 A5 DO 0418 707 MOVL UCBSL_DEVDEPN2(R5),UCBSL_DEVDEPN2(R0) ; "UCBSL_TT_DEVDP1"
      40 A0 40 A5 DO 041D 708 MOVL UCBSB_DEVCLASS(R5),UCBSB_DEVCLASS(R0) ; CLASS,TYPE,BUFSIZE
      0422 709
      0422 710 ; THIS ROUTINE COMPLETES SET AND SENSE CHARACTERISTICS OPERATIONS
      0422 711 ; AND RETURNS STATUS VALUES IN THE IOSB
      0422 712 ;
      0422 713 DO_EXIT:
      51 00F6 C5 50 00F2 C5 DO 0422 714 MOVL UCBSW TT_SPEED-2(R5),R0; RETURN SPEED
      FF3FFFFFF 8F CB 0427 715 BICL3 #^C<<UCBSM TT_PARTY!UCBSM TT_ODD>>@16>,UCBSB_TT_PARITY-2(R5),R1;
      51 00F6 C5 50 01 80 0431 716 MOVW UCBSB_TT_CRFIL(R5),R1 ; INSERT FILL DATA
      02F9 31 80 0436 717 MOVW #SS$ NORMAL,R0 ; SET STATUS
      043C 718 BRW TTY$DONE
      043C 719
      043C 720 NOPRIV_EXIT:
```


TTYSTRSTP
V04-000

D 7
- Terminal driver start/stop I/O routine 16-SEP-1984 02:18:30 VAX/VMS Macro V04-00 Page 18
START_IO ACTION ROUTINES 5-SEP-1984 04:17:09 [TTDRVR.SRC]TTYSTRSTP.MAR;1 (13)

| | | | | | | | | |
|------|----|------|------|-----|------|-----------------|---|-------------|
| 50 | 24 | D0 | 043C | 721 | MOVL | #SS\$_NOPRIV,R0 | : | SET NO PRIV |
| | 51 | D4 | 043F | 722 | CLRL | R1 | : | CLEAR R1 |
| 02F1 | 31 | 0441 | 723 | | BRW | TTYSDONE | | |
| | | 0444 | 724 | | | | | |

```

0444 726 :
0444 727 : WRITE OPERATION
0444 728 :
0444 729 DO_WRITE:
0444 730 :
0444 731 : Control only comes here in the case of half duplex writes. Full
0444 732 : duplex writes use the TTY$WRTSTARTIO entry point.
0444 733 :
53 2C A3 DO 0444 734 MOVL IRPSL SVAPTE(R3), R3 : Get addr of write block
00000532'EF 9F 0448 735 PUSHAB TTY$STARTOUTPUT : if write is started, control
: will return to STARTOUTPUT
0040 30 044E 736 BSBW WRTSTARTIO : if queued, control will return
05 0451 738 RSB : here. Return to caller.

```

```

0452 740 .SBTTL TTY$WRTSTARTIO - Starts or queues a write operation
0452 741
0452 742 :++
0452 743
0452 744 Functional description:
0452 745
0452 746 If called from an FDT routine (or from EXE$BRDCST),
0452 747 TTY$WRTSTARTIO first raises to device IPL, and then calls the
0452 748 internal routine. All other code enters through the WRTSTARTIO
0452 749 entry point.
0452 750
0452 751 If a write is occurring, the routine queues the write buffer.
0452 752 If a read is occurring, but the buffer header specifies
0452 753 write-breakthrough, the routine starts the write.
0452 754 If a read is occurring, but no characters have been received
0452 755 yet, the routine starts the write.
0452 756 Otherwise, the routine queues the write buffer.
0452 757
0452 758 To start the write operation, the routine writes the address
0452 759 of the buffer in UCB$L_IT_WRTBUF, sets and clears various
0452 760 state bits, and returns.
0452 761
0452 762 To queue the buffer, the routine inserts the buffer address at
0452 763 the end of the queue unless the header specifies write-
0452 764 breakthrough. In the latter case, the buffer address is inserted
0452 765 after the last write-breakthrough request in the queue.
0452 766
0452 767 Returning from WRTSTARTIO is odd. The routine assumes that 0(SP)
0452 768 is the address to return to if the write is to start now.
0452 769 If the routine instead queues the write, the routine pops this
0452 770 start-write address of the stack, and returns to the real
0452 771 caller.
0452 772
0452 773 Inputs:
0452 774
0452 775 R3 - address of the write buffer
0452 776 R5 - address of the UCB
0452 777
0452 778 Implicit inputs:
0452 779
0452 780 The write buffer consists of a header, and an optional message
0452 781 buffer. For broadcast messages, the message buffer is absent.
0452 782 TTY$L_WB_FR3 is 0 for a normal broadcast and 1 for and ANSI
0452 783 broadcast or one that specified norefresh.
0452 784
0452 785 Outputs:
0452 786
0452 787 If the broadcast message is rejected, the TTY$L_WB_END field
0452 788 of the write packet is zeroed.
0452 789
0452 790 R0 - preserved
0452 791 R1 - scratch
0452 792 R2 - address of UCB state bits
0452 793 R3 - address of buffer
0452 794 R4 - if packet is started, address of IRP or 0
0452 795 - if packet is queued, scratch
0452 796 R5 - address of UCB

```



```
0452 797 :
0452 798 : Implicit outputs:
0452 799 :
0452 800 : Buffer may be entered in queue.
0452 801 :
0452 802 : If write operation is started,
0452 803 : UCB$$_TT_WRTBUF - address of buffer
0452 804 : UCB$$_TT_STATE - write bit, and other bits from IRP are set
0452 805 : control-0 may be canceled
0452 806 : UCB$$_DEVDEPEND - mailbox may be enabled
0452 807 :
0452 808 :--
0452 809 :
0452 810 TTY$WRTSTARTIO::
51 00A0 C5 D0 0452 811 MOVL UCB$$_TL_PHYUCB(R5),R1 : Start or queue write.
: 22 13 0452 812 BEQL 308 : GET PUCB ADDRESS
: 55 51 D0 0452 813 MOVL R1,R5 : NONE CURRENTLY EXISTS
: 24 A3 D5 0452 814 TSTL TTY$$_WB_IRP(R3) : SWITCH TO PUCB CONTEXT
: 0C 13 0452 815 BEQL 208 : Is this a broadcast?
: : 0452 816 10$: : YES, SPECIAL CASE
: : 0452 817 : BSBW TTY$$_LOCK : Acceptable packet.
: : 0452 818 : PUSHAB TTY$$_STARTOUTPUT : Raise to DIPL, get states.
: : 0452 819 : : Set up return address to
: : 0452 820 : BSBW WRTSTARTIO : start the output.
: : 0452 821 : RSB : Start or queue the packet.
: : 0452 822 : : If packet queued, control
: : 0452 823 : : returns here, so return to
: : 0452 824 : : caller.
: : 0452 825 : :
: : 0452 826 20$: : INTERNAL BROADCAST PACKET.
: : 0452 827 : : CHECK FOR DISABLE
: : 0452 828 : :
: : 0452 829 : BITL #TTY$$_PASSALL:- : Test for passall and/or
: : 0452 830 : TTY$$_NOBRDCST,- : nobroadcast modes set in the
: : 0452 831 : UCB$$_DEVDEPEND(R5) : term's UCB (ignore NOECHO).
: : 0452 832 : BEQL 108 : Continue if not set.
: : 0452 833 : CLRL TTY$$_WB_END(R3) : Zero end address to indicate
: : 0452 834 : : failure to EXE$$_BRDCST.
: : 0452 835 : RSB : And return to EXE$$_BRDCST.
: : 0452 836 : :
: : 0452 837 : LUCB CURRENTLY DETACHED
: : 0452 838 : COMPLETE THE WRITE
: : 0452 839 : ASSUME IRP$$_IOST1+4 EQ IRP$$_IOST2
: : 0452 840 : 30$: :
: : 0452 841 : MOVL TTY$$_WB_IRP(R3),R1 : GET IRP ADDRESS
: : 0452 842 : BEQL 258 : INTERNAL BROADCAST, REJECT IT.
: : 0452 843 : MOVL R1,R3 : GET IRP ADDRESS
: : 0452 844 : CLRQ IRP$$_IOST1(R3) : INIT IOSB RETURN
: : 0452 845 : MOVW #SS$$_NORMAL,IRP$$_IOST1(R3)
: : 0452 846 : JMP G*COM$$_POST
: : 0452 847 :
: : 0452 848 WRTSTARTIO: : Checks for start or queue.
: : 0452 849 :
: : 0452 850 : :
: : 0452 851 : : Inputs:
: : 0452 852 : :
: : 0452 853 : : R2 - address of state bits longword
```

| | | | | | | | | |
|------|------|----|------|------|-----|--------------|--|---------------------------------------|
| | | | 0491 | 854 | : | R3 | - address of write packet | |
| | | | 0491 | 855 | : | R5 | - address of the device's UCB | |
| | | | 0491 | 856 | : | | | |
| | | | 0491 | 857 | : | 0(SP) | - address to return if write is queued | |
| | | | 0491 | 858 | : | 4(SP) | - address to return to if write is started | |
| | | | 0491 | 859 | : | | | |
| | | | 0491 | 860 | : | | | |
| | | | 0491 | 861 | : | PUSHR | #M<R0> | : Save a register. |
| 50 | 00CC | 01 | BB | 0493 | 862 | MOVAB | UCB\$\$_TT_WFLINK(R5),R0 | : Get address of write queue. |
| 54 | 24 | A3 | D0 | 0498 | 863 | MOVL | TTY\$\$_WB_IRP(R3),R4 | : Get address of IRP. |
| | | | | 049C | 864 | IF_STATE | - | : If writing is in progress, |
| | | | | 049C | 865 | | WRITE,QUEUE_PKT | : just queue the packet. |
| | | 54 | D5 | 04A0 | 866 | TSTL | R4 | : See if the packet has an IRP. |
| | | 42 | 13 | 04A2 | 867 | BEQL | START_PKT | : If not, just start the packet. |
| | | | | 04A4 | 868 | IF_NOT_STATE | = | : If not in a read state, |
| | | | | 04A4 | 869 | | READ,START_PKT | : go ahead and start the packet. |
| | | | | 04A8 | 870 | IF_STATE | - | : If noecho read, no blocking |
| | | | | 04A8 | 871 | | NOECHO,START_PKT | : so start the write |
| | | 09 | E0 | 04AC | 872 | BBS | #IOSV_BREAKTRU,- | |
| 35 | 20 | A4 | | 04AE | 873 | | IRPSW_FUNC(R4),START_PKT | : Start if break thru write. |
| 51 | 78 | A5 | D0 | 04B1 | 874 | MOVL | UCB\$\$_SVAPTE(R5),R1 | : get the read packet address |
| | 3C | A1 | B5 | 04B5 | 875 | TSTW | TTY\$\$_RB_TXTOFF(R1) | : and check if we have started typing |
| | | 2C | 13 | 04B8 | 876 | BEQL | START_PKT | : go start the packet. |
| | | 19 | 11 | 04BA | 877 | BRB | QUEUE_LAST | : Otherwise, queue packet at end |
| | | | | 04BC | 878 | | | : of queue. |
| | | | | 04BC | 879 | | | |
| | | 54 | D5 | 04BC | 880 | QUEUE_PKT: | | |
| | | 15 | 12 | 04BE | 881 | TSTL | R4 | : If an IRP is associated, |
| 54 | 50 | D0 | | 04C0 | 882 | BNEQ | QUEUE_LAST | : queue packet at end of queue. |
| | | | | 04C3 | 883 | MOVL | R0,R4 | : Make a copy of queue head. |
| | | | | 04C3 | 884 | | | |
| | | | | 04C3 | 885 | 10\$: | | |
| 51 | 64 | D0 | | 04C3 | 886 | MOVL | TTY\$\$_WB_FLINK(R4),R1 | : Get first queue entry. |
| 50 | 51 | D1 | | 04C6 | 887 | CMPL | R1,R0 | : See if at end of queue. |
| | 0A | 13 | | 04C9 | 888 | BEQL | QUEUE_LAST | : If yes, put at end of queue. |
| | 24 | A1 | D5 | 04CB | 889 | TSTL | TTY\$\$_WB_IRP(R1) | : Else, see if this entry has an |
| | | | | 04CE | 890 | | | : associated IRP. |
| | | 09 | 12 | 04CE | 891 | BNEQ | INSERT_PKT | : If yes, branch to insert |
| | | | | 04D0 | 892 | | | : packet before it. |
| 54 | 51 | D0 | | 04D0 | 893 | MOVL | R1,R4 | : Otherwise, go on to next |
| | EE | 11 | | 04D3 | 894 | BRB | 10\$ | : entry in queue. |
| | | | | 04D5 | 895 | | | |
| | | | | 04D5 | 896 | QUEUE_LAST: | | : Queue at end of queue. |
| 54 | 04 | A0 | D0 | 04D5 | 897 | MOVL | TTY\$\$_WB_BLINK(R0),R4 | : Get back pointer. |
| | | | | 04D9 | 898 | | | |
| | | | | 04D9 | 899 | INSERT_PKT: | | |
| | | 63 | 0E | 04D9 | 900 | INSQUE | TTY\$\$_WB_FLINK(R3),- | : Insert new packet in the |
| | | 64 | | 04DB | 901 | | TTY\$\$_WB_FLINK(R4) | : queue. |
| | | 01 | BA | 04DC | 902 | POPR | #M<R0> | : Remove saved register and |
| 51 | 6E | D0 | | 04DE | 903 | MOVL | (SP),R1 | : get queued address |
| 5E | 08 | C0 | | 04E1 | 904 | ADDL | #8,SP | : clean stack |
| | 61 | 17 | | 04E4 | 905 | JMP | (R1) | : return to queued address |
| | | | | 04E6 | 906 | | | |
| | | | | 04E6 | 907 | START_PKT: | | : Start the packet. |
| 00D4 | C5 | 53 | D0 | 04E6 | 908 | MOVL | R3,UCB\$\$_TT_WRTBUF(R5) | : Point to packet from UCB. |
| | | | | 04EB | 909 | SET_STATE | - | : Set the write state. |
| | | | | 04EB | 910 | | WRITE | |

| | | | | | | | | | |
|----|----|----------|----|------|------|-----------|------------------------------------|---|---------------------------------------|
| | | 54 | D5 | 04EF | 911 | TSTL | R4 | : | If this write does not have an |
| | | 31 | 13 | 04F1 | 912 | BEQL | 20\$ | : | IRP, don't check IRP fields. |
| | 62 | 40 | A4 | C8 | 04F3 | BISL | IRPSQ_TT_STATE(R4),(R2) | : | Set write state bits. |
| 04 | A2 | 44 | A4 | C8 | 04F7 | BISL | IRPSQ_TT_STATE+4(R4),4(R2) | : | Set write state bits. |
| | | 38 | A4 | D4 | 04FC | CLRL | IRPSL_MEDIA(R4) | : | Set up IRP for completion. |
| | | 07 | E1 | 04FF | 916 | BBC | #IOSV_ENABLMBX,- | : | Branch if enable-mailbox |
| | 15 | 20 | A4 | 0501 | 917 | | IRPSW_FUNC(R4),10\$ | : | is not requested. |
| | | | | 0504 | 918 | | | | |
| | 51 | 00C0 | C5 | D0 | 0504 | MOVL | UCBSL_TT_LOGUCB(R5),R1 | : | GET LOGICAL UCB ADDRESS |
| 44 | A5 | 00010000 | 8F | CA | 0509 | BICL | #TTSM_MBXDSABL,UCBSL_DEVDEPEND(R5) | : | CLEAR MAILBOX DISABLED PHYSICAL |
| 44 | A1 | 00010000 | 8F | CA | 0511 | BICL | #TTSM_MBXDSABL,UCBSL_DEVDEPEND(R1) | : | CLEAR MAILBOX DISABLED LOGICAL |
| | | | | 0519 | 922 | | | | |
| | | | | 0519 | 923 | | | | |
| | | 06 | E1 | 0519 | 924 | BBC | #IOSV_CANCTRLO,- | : | Branch if cancel control-0 |
| | 11 | 20 | A4 | 051B | 925 | | IRPSW_FUNC(R4),30\$ | : | is not requested. |
| | | | | 051E | 926 | CLR_STATE | - | : | Clear control-0 state. |
| | | | | 051E | 927 | | CTRLO | | |
| | | 0B | 11 | 0522 | 928 | BRB | 30\$ | : | And start the output. |
| | | | | 0524 | 929 | | | | |
| | | | | 0524 | 930 | | | | |
| | | | | 0524 | 931 | : | Start a broadcast packet. | | |
| | | | | 0524 | 932 | : | | | |
| | | | | 0524 | 933 | : | | | |
| | | | | 0524 | 934 | 20\$: | | | |
| | 0B | A3 | 94 | 0524 | 935 | CLRB | TTY\$B_WB_FIPL(R3) | : | Indicate block free to fork (for DMA) |
| 04 | 10 | A3 | E9 | 0527 | 936 | BLBC | TTY\$B_WB_FR3(R3),30\$ | : | Branch if ANSI broadcast or norefresh |
| | | | | 052B | 937 | SET_STATE | - | | |
| | | | | 052B | 938 | | <REFRSH> | : | Set refresh read |
| | | | | 052F | 939 | 30\$: | | : | Go output buffer. |
| | 03 | BA | | 052F | 940 | POPR | #*M<R0,R1> | : | Restore saved register |
| | | | | 0531 | 941 | | | : | and queued address. |
| | | | 05 | 0531 | 942 | RSB | | : | And return to caller. |


```
0532 944 .SBTTL TTY$STARTOUTPUT - START OUTPUT OPERATION ON UNIT
0533 945
0534 946 :++
0535 947 : TTY$STARTOUTPUT - START OUTPUT ON UNIT
0536 948
0537 949 : FUNCTIONAL DESCRIPTION:
0538 950
0539 951 : THIS ROUTINE IS USED TO INITIATE OUTPUT ON A UNIT. THIS OPERATION STARTS
0540 952 : THE FLOW OF DATA EVEN IN THE CASE OF READS. THE ACTION IS TO TEST THE
0541 953 : STATE OF INTERRUPT EXPECTED. IF AN INTERRUPT IS EXPECTED, THEN NOTHING NEED BE DON
0542 954 : BECAUSE A SUBSEQUENT INTERRUPT WILL CONTINUE APPROP. WITH THE CURRENT STATE.
0543 955 : IF NO INTERRUPT IS EXPECTED, THEN THE TTY$GETNEXTCHAR ROUTINE IS ENTERED TO RETURN
0544 956 : THE NEXT CHARACTER(S) FOR THE UNIT. THEN IF AVAILABLE THE PORT DRIVER
0545 957 : STARTIO ROUTINE IS ENTERED.
0546 958 : THIS OPERATION IS IDENTICAL TO THE OPERATION OF AN OUTPUT READY INTERRUPT.
0547 959
0548 960 : INPUTS:
0549 961
0550 962 : R2 = ADDRESS OF THE UNIT STATE VECTOR
0551 963 : R5 = UCB ADDRESS
0552 964
0553 965 : OUTPUTS:
0554 966
0555 967 : NONE
0556 968
0557 969 :--
0558 970 TTY$STARTOUTPUT: : START OUTPUT
0559 971 BBS #UCB$V.INT,UCB$W.STS(R5),100$ : LEAVE HERE IF INTERRUPT EXPECTED
0560 972 MOVL UCB$L.TT.PORT(R5),R0 : GET THE PORT'S VECTOR TABLE ADDRESS
0561 973 BSBW TTY$GETNEXTCHAR : GET NEXT CHARACTER FOR UNIT
0562 974 BLBC UCB$B.TT.OUTPUT(R5),100$ : LEAVE IF NOTHING TO OUTPUT
0563 975 JMP @PORT_STARTIO(R0) : START OUTPUT ON LINE
0564 976 RSB : RETURN
```

10 64 A5 01 E0 0532 970
50 0118 C5 D0 0537 971
FAC1 30 053C 972
03 010B C5 E9 053F 973
00 B0 17 0544 974
05 0547 975 100\$:

```
0548 977 .SBTTL TTY$GETNXTWRITE - Start next write or restart read
0548 978
0548 979 :++
0548 980
0548 981 Functional description:
0548 982
0548 983 This routine gains control at device IPL on return from the
0548 984 VMS fork queuing routine. The routine tries to restart a
0548 985 suspended but now active read, or to dequeue and start the
0548 986 next write request vis WRTSTARTIO.
0548 987
0548 988 The routine always returns to the caller of TTY$WRITEDONE,
0548 989 TTY$READONE, or BRDCST in TTYCHARO. This caller is usually
0548 990 GETNEXTCHAR, so setting states causes the driver to go on
0548 991 echoing and outputting.
0548 992
0548 993 Inputs:
0548 994
0548 995 0(SP) - address of the UCB state vector
0548 996 4(SP) - address of the UCB
0548 997
0548 998 Outputs:
0548 999
0548 1000 R2 - address of the UCB state vector
0548 1001 R3 - address of a write buffer if writing is to begin
0548 1002 R5 - address of the UCB
0548 1003
0548 1004 The 2 named inputs are removed from the stack.
0548 1005
0548 1006 :--
0548 1007
24 BA 0548 1008 TTY$GETNXTWRITE::
0548 1009 POPR #*M<R2,R5> : Check for a new write.
054A 1010 : Restore UCB state address and
054A 1011 IF_NOT_STATE - : UCB address.
054A 1012 READ,10$ : If not in a read state, just
054E 1013 IF_STATE - : branch forward.
054E 1014 NOECHO,10$ : If noecho, don't block writes
0552 1015 CMPL UCB$$_TT_WFLINK(R5),- :
0556 1016 UCB$$_TT_WBLINK(R5) : queue empty?
0559 1017 BEQL 5$ : Branch if yes
055B 1018 MOVL UCB$$_TT_WFLINK(R5),R3 : Fetch address of next irp
0560 1019 BBS #IOSV_BREAKTHRU - :
0562 1020 5$: MOVL IRP$W_FUNC(R3),10$ : Start if break thru write.
0565 1021 MOVL UCB$$_SVAPTE(R5),R3 : get the read packet address
0569 1022 TSTW TTY$W_RB_TXTOFF(R3) : see if any input
056C 1023 : has been received.
056C 1024 BNEQ 20$ : If yes, go restart read.
056E 1025
056E 1026 10$: IF_STATE WRITE,30$ : if we are writing then don't get the
0572 1027 : next write
0572 1028 : Otherwise, look for a write.
0572 1029 REMQUE @UCB$$_TT_WFLINK(R5),R3 : Get a new write buffer.
0577 1030 BVS 20$ : Branch if no buffers exist.
0579 1031 PUSHAB 30$ : Save a write start return
057F 1032 : address.
057F 1033 BSBW WRTSTARTIO : Start the write.
```

TTYSTRSTP
V04-000

L 7

- Terminal driver start/stop I/O routine 16-SEP-1984 02:18:30 VAX/VMS Macro V04-00 Page 26
TTY\$GETNXTWRITE - Start next write or re 5-SEP-1984 04:17:09 [TTDRVR.SRC]TTYSTRSTP.MAR;1 (17)

| | | | | | | | |
|-------|----|------|------|-------|------|----------------|-----------------------------|
| | 05 | 0582 | 1034 | | RSB | | : Return to GETNEXTCHAR. |
| | | 0583 | 1035 | | | | |
| FA7A' | 30 | 0583 | 1036 | 20\$: | BSBW | TTY\$RESTARTIO | : Restart the read, if any. |
| | | 0583 | 1037 | | | | |
| | | 0586 | 1038 | | | | : Joint read/write return. |
| | 05 | 0586 | 1039 | 30\$: | | | : Return. |
| | | 0586 | 1040 | | RSB | | |


```
0587 1042 .SBTTL TTY$WRITEDONE - Complete a write operation
0587 1043
0587 1044 ++
0587 1045 TTY$WRITEDONE - WRITE OPERATION DONE
0587 1046
0587 1047 FUNCTIONAL DESCRIPTION:
0587 1048
0587 1049 This routine creates a fork process to complete the write, and
0587 1050 checks for another write packet to start up.
0587 1051
0587 1052 INPUTS:
0587 1053
0587 1054 R2 = ADDRESS OF THE UNIT STATE VECTOR
0587 1055 R5 = UCB ADDRESS
0587 1056
0587 1057 TTY$W_WB_STATUS - status of operation
0587 1058 TTY$W_WB_BCNT - number of bytes transferred
0587 1059
0587 1060 OUTPUTS:
0587 1061
0587 1062 R2,R5 ARE PRESERVED.
0587 1063
0587 1064 ;--
0587 1065
0587 1066 TTY$WRITEDONE:: ; Complete write operation.
0587 1067
0587 1068
0587 1069 This routine used to start by clearing a whole raft of state bits.
0587 1070 I only turn off write-related bits, and I do that in TTY$GETNXTWRITE.
0587 1071 The bits I no longer modify are:
0587 1072
0587 1073 READ, DEL, XON, EOL, PROMPT, CTRLR, NOFLTR, ESC, ESC_O, and
0587 1074 BADE$C
0587 1075
0587 1076
0587 1077
0587 1078 24 BB 0587 1078 PUSHR #*M<R2,R5> ; Save state and UCB address.
0589 1079 14$:
0589 1080
0589 1081 53 00D4 C5 D0 0589 1081 MOVL UCB$L_TT_WRTBUF(R5),R3 ; Get address of write buffer.
058E 1082
058E 1083
058E 1084 : NEW LINE MODIFIER
058E 1085
058E 1086 54 24 A3 D0 058E 1086 MOVL TTY$L_WB_IRP(R3),R4 ; Get address of associated IRP.
0592 1087 BEQL 10$
0594 1088 07 20 A4 0A E1 0594 1088 BBC #10$V NEWLINE,IRP$W_FUNC(R4),10$; NO NEWLINE THEN DON'T ADD A THING
0599 1089 SET_STATE <SEDLF,SKIPLF,NLS>
05A0 1090 10$:
05A0 1091 CLR_STATE - ; Clear the write bits.
05A0 1092 <WRITE,WRTALL>
05AB 1093 9D AF 9F 05AB 1093 PUSHAB TTY$GETNXTWRITE ; Return address after queuing fork
05AB 1094
05AB 1095 WRITEPOST:
05AB 1096
05AB 1097 0B A5 90 05AB 1097 MOVB UCB$B_FIPL(R5),- ; Set up fork IPL in the buffer
05AE 1098 0B A3 05AE 1098 TTY$B_WB_FIPL(R3) ; block.
```

```
54 24 A3 D0 05B0 1099      MOVL  TTY$WB_IRP(R3),R4      ; Get address of associated IRP.
      08 12 05B4 1100      BNEQ  5$                      ; one there then continue
      06 90 05B6 1101      MOVW  #IPL$_QUEUEAST,-          ; for broadcast fork to ipl6
      0B A3 05B8 1102      TTY$WB_FIPL(R3)
      7E D4 05BA 1103      clrl  -(sp)                    ; no irp then no process to fork to
      03 11 05BC 1104      brb  7$
      05BE 1105 5$:
      0C A4 DD 05BE 1106      PUSHL IRP$P_PID(R4)           ; FORK ON THE PID OF THE IO OWNER
      55 53 D0 05C1 1107 7$:      MOVL  R3,R5              ; Setup fork block address.
00000000'EF 16 05C4 1108      JSB   TTY$SYNCH              ; Create a fork process.
      05CA 1109
      05CA 1110
      05CA 1111      : This is the write completion fork process. Registers are as follows:
      05CA 1112      R4      - address of IRP
      05CA 1113      R5      - address of write buffer (TWP)
      05CA 1114
      05CA 1115
      05CA 1116
      53 54 D0 05CA 1117      MOVL  R4,R3                  ; Need IRP in R3 for I/O post.
      54 13 05CD 1118      BEQL  100$
      05CF 1119
      05CF 1120      .IF DF  CAS_MEASURE_IOT
      05CF 1121
      05CF 1122      : ACCUMULATE STATISTICS ON NUMBER OF CHARACTERS AND I/OS TO TERMINALS.
      05CF 1123
      05CF 1124      BSBB  TTSTATS                        ; CALL STATISTICS ROUTINE.
      05CF 1125
      05CF 1126      .ENDC
      05CF 1127
      05CF 1128
      05CF 1129      : NOTE: IRP$P_MEDIA = IRP$P_IOST1
      05CF 1130      : NOTE: terminal position is 0-based; interface position is 1-based
      05CF 1131
      05CF 1132
      54 55 D0 05CF 1133      MOVL  R5,R4                  ; Put buffer address in R4.
      38 A3 3C 05D2 1134      MOVZWL IRP$P_MEDIA(R3),-      ; number of lines output for the
      3C A3 05D5 1135      IRP$P_IOST2(R3)                ; write QIO, and zero other values
      28 A4 D0 05D7 1136      MOVL  TTY$WB_STATUS(R4),-    ; move status and count of bytes
      38 A3 05DA 1137      IRP$P_IOST1(R3)                ; transferred into IOSB
      05DC 1138
      55 1C A3 D0 05DC 1139      MOVL  IRP$P_UCB(R3),R5     ; Regain LUCB address.
      55 00A0 C5 D0 05E0 1140      MOVL  UCB$P_TL_PHYUCB(R5),R5 ; Switch to Physical context
      1D 13 05E5 1141      BEQL  15$                      ; Disconnect has occurred!
      00FC C5 B1 05E7 1142      CMPW  UCB$P_TT_CURSOR(R5),- ; Is cursor marker beyond the right-
      42 A5 05EB 1143      UCB$P_DEVBUSIZ(R5)              ; hand edge of screen?
      09 1E 05ED 1144      BGEQU  12$                      ; Branch if cursor has gone too far.
      00FC C5 A1 05EF 1145      ADDW3 UCB$P_TT_CURSOR(R5),- ; Else return cursor column position,
      3E A3 01 05F3 1146      #1,IRP$P_IOST2+2(R3)        ; adjusted for zero offset, in IOSB.
      05 11 05F6 1147      BRB  14$                      ; Continue building IOSB.
      42 A5 B0 05F8 1148 12$:      MOVW  UCB$P_DEVBUSIZ(R5),- ; If necessary, return cursor column
      3E A3 05FB 1149      IRP$P_IOST2+2(R3)              ; position in IOSB as right-hand edge.
      00FE C5 B1 05FD 1150 14$:      ADBB3 UCB$P_TT_LINE(R5),- ; move line position into IOSB
      3F A3 01 0601 1151      #1,IRP$P_IOST2+3(R3)
      0604 1152
      08 A4 B0 0604 1153 15$:      MOVW  TTY$WB_SIZE(R4),-  ; Move size of buffer into IRP
      30 A3 0607 1154      IRP$P_BOFF(R3)                ; to record quota used.
      55 1C A3 D0 0609 1155      MOVL  IRP$P_UCB(R3),R5     ; Restore logical UCB address
```

| | | | | | | | | | |
|-------------|-------|----|------|------|--------|--------|-------------------------|---|---------------------------------------|
| 52 A5 | 53 | 01 | 060D | 1156 | | CMPL | R3,UCB\$\$_IRP(R5) | : | Is this the current write |
| | 06 | 13 | 0611 | 1157 | | BEQL | 30\$ | : | blocking the i/o queue? |
| 00000000'GF | | | 0613 | 1158 | | | | | |
| | | 17 | 0613 | 1159 | 20\$: | JMP | G^COM\$POST | : | Full duplex: complete write |
| | | | 0619 | 1160 | | | | | |
| 50 | 38 A3 | 7D | 0619 | 1161 | 30\$: | | | : | Half duplex: |
| | | | 0619 | 1162 | | MOVQ | IRP\$\$_MEDIA(R3),R0 | : | Load IOST1 and IOST2 in R0,R1 |
| | | | 061D | 1163 | | REQCOM | | : | Complete request and get next |
| | | | 0623 | 1164 | | | | : | entry in system queue. |
| | | | 0623 | 1165 | 100\$: | | | | |
| 53 | 20 A5 | D0 | 0623 | 1166 | | MOVL | TTY\$\$_WB_END(R5),R3 | : | GET THE ADDRESS OF THE LAST CHARACTER |
| | 2C B5 | 17 | 0627 | 1167 | | JMP | @TTY\$\$_WB_RETADDR(R5) | : | Want fork process to gain control |
| | | | 062A | 1168 | | | | : | string for fork process use. |
| | | | 062A | 1169 | | | | | |
| | | | 062A | 1170 | | | | | |


```

062A 1172      .SBTTL  TTY$WRITEPOST - QUEUE A WRITE COMPLETION
062A 1173
062A 1174      :++
062A 1175      : TTY$WRITEPOST - QUEUE A WRITE COMPLETION
062A 1176
062A 1177      : FUNCTIONAL DESCRIPTION:
062A 1178
062A 1179      :     THIS ROUTINE FORKS ON A TWP TO COMPLETE A QUEUED WRITE OPERATION
062A 1180      :     BOTH HALF AND FULL DUPLEX.
062A 1181
062A 1182      : INPUTS:
062A 1183
062A 1184      :     R4 = TWP ADDRESS
062A 1185      :     R5 = UCB ADDRESS
062A 1186
062A 1187      :     UCB$W_BOFF - STATUS OF OPERATION
062A 1188
062A 1189      : OUTPUTS:
062A 1190
062A 1191      :     R0,R1,R2,R3,R5 ARE PRESERVED
062A 1192      :--
062A 1193
062A 1194      TTY$WRITEPOST::
062A 1195
062A 1196      : PUSHR  #*M<R3,R5>      : SAVE REGISTERS
062C 1197      : MOVL   R4,R3      : TWP ADDRESS
062F 1198      : CLRW   TTY$W_B BCNT(R3)  : NONE TRANSFERED
0632 1199      : MOVW   UCB$W_BOFF(R5),-  : SAVE COMPLETION STATUS
0635 1200      : TTY$W_B STATUS(R3)
0637 1201      : BSBW   WRITEPOST      : QUE THE FORK
063A 1202      : POPR   #*M<R3,R5>
063C 1203      : RSB
063D 1204
063D 1205

```

```

53  28  BB
    54  DO
    2A  A3  B4
    7C  A5  B0
    28  A3
    FF  71  30
    28      BA
        05

```

```

063D 1207      .IF DF CAS_MEASURE_IOT
063D 1208      :
063D 1209      : Subroutine to accumulate statistics on the number of
063D 1210      : the number of characters read and written to terminals
063D 1211      :
063D 1212      :
063D 1213      TSTATS:BLBC      G^PMS$GL_DOSTATS,40$      : IF FLAG SET, BYPASS STATISTICS CODE
063D 1214      MOVZWL      IRPSW_BCNT(R3),R1      : GET # CHARACTERS TRANSFERRED.
063D 1215      DIVL3      #5,R1,R0      : STATISTICS ARE KEPT IN INCREMENTS
063D 1216      : OF 5 CHARACTERS.
063D 1217      CMPL      #9,R0      : LAST ENTRY IN TABLE IS FOR I/Os
063D 1218      : OF >= 45 CHARACTERS.
063D 1219      BGEQ      10$
063D 1220      MOVL      #9,R0
063D 1221      10$: CMPZV      #IRPSV_FCODE,#IRPSS_FCODE,IRPSW_FUNC(R3),#TTY$C_FC_READ
063D 1222      : CHECK IF JUST FINISHED A READ OR WRITE.
063D 1223      BNEQ      20$      : BRANCH FOR WRITE
063D 1224      :
063D 1225      : COMPILE STATISTICS FOR READ
063D 1226      :
063D 1227      INCL      G^PMS$AL_READTBL[R0]      : INCREMENT APPROPRIATE RANGE.
063D 1228      INCL      G^PMS$GL_TREADS      : INCREMENT READ COUNT
063D 1229      ADDL2      R1,G^PMS$GL_READCNT      : INCREMENT TOTAL COUNT FOR CHARACTERS
063D 1230      BRB      40$
063D 1231      :
063D 1232      : COMPILE STATISTICS FOR WRITE
063D 1233      :
063D 1234      20$: INCL      G^PMS$AL_WRIETBL[R0]      : INCREMENT APPROPRIATE RANGE.
063D 1235      INCL      G^PMS$GL_TWRTES      : INCREMENT WRITE COUNT
063D 1236      ADDL2      R1,G^PMS$GL_WRTCNT      : INCREMENT TOTAL COUNT FOR CHARACTERS
063D 1237      : WRITTEN.
063D 1238      40$: RSB      : RETURN TO CALLER.
063D 1239      :
063D 1240      .ENDC

```

```
063D 1242 .SBTTL TTY$READONE - READ OPERATION DONE
063D 1243 :++
063D 1244 : TTY$READONE - READ I/O OPERATION DONE
063D 1245 :
063D 1246 : FUNCTIONAL DESCRIPTION:
063D 1247 :
063D 1248 : THIS ROUTINE IS ENTERED TO COMPLETE THE CURRENT READ OPERATION.
063D 1249 : THE ACTION IS TO RESET THE STATE OF THE UNIT TO REFLECT THE CHANGE AND TO
063D 1250 : FORK ON THE IRP TO COMPLETE THE PROCESSING.
063D 1251 :
063D 1252 : INPUTS:
063D 1253 :
063D 1254 : R2 = ADDRESS OF THE UNIT STATE VECTOR
063D 1255 : R5 = UCB ADDRESS
063D 1256 :
063D 1257 : UCB$W_BOFF = STATUS WORD
063D 1258 : UCB$W_BCNT = COUNT OF TRANSFER
063D 1259 :
063D 1260 : IRP$L_MEDIA(CURRENT PACKET) = TERMINATOR AND TERMINATOR SIZE
063D 1261 :
063D 1262 : OUTPUTS:
063D 1263 :
063D 1264 :
063D 1265 : NONE
063D 1266 : --
063D 1267 : enable lsb
063D 1268 TTY$READONE:: : READ I/O DONE
063D 1269 BBC #TT$V_READSYNC,UCB$L_DEVDEPEND(R5),10$; BR IF NOT READSYNC
0642 1270 BSBW TTY$XOFF : SEND XOFF
0645 1271 10$: BICW #UCB$M_TT_TIMO,UCB$W_DEVSTS(R5); CLEAR TIMEOUT ENABLED
0649 1272 :
0649 1273 : SET UP ERRORS ON ESCAPE SEQUENCES
0649 1274 :
0649 1275 : IF NOT_STATE ESC,15$ : IF NOT ESCAPE THEN BR
064D 1276 MOVW #SS$_PARTESCAPE,UCB$W_BOFF(R5); ASSUME PARTIAL ESCAPE SEQUENCE
0653 1277 MOVL UCB$L_SVAPTE(R5),R4 : GET THE ADDRESS OF THE READ PACKET
0657 1278 MOVL UCB$L_IRP(R5),R3 : ADDRESS CURRENT PACKET
065B 1279 MOVZBW IRP$L_MEDIA+2(R3),R3 : MAKE THE ESCAPE SEQUENCE COUNT A WORD
065F 1280 SUBW R3,TTY$W_RB_TXTOFF(R4) : SUBTRACT OUT TERMINATOR LENGTH
0663 1281 15$: IF NOT_STATE BADESC,20$ : ESCAPE SYNTAX CORRECT?
0667 1282 MOVW #SS$_BADESCAPE,UCB$W_BOFF(R5); SET STATUS FOR IMPROPER ESCAPE SEQ
0668 1283 :
0668 1284 : RESET PASSALL AND NOECHO IF MODES
0668 1285 :
0668 1286 20$:
0668 1287 :
0668 1288 : .IF DF CAS_MEASURE_IOT
0668 1289 :
0668 1290 BLBC G^PM$SGL_DOSTATS,25$ : IF FLAG SET, BYPASS STATISTICS CODE
0668 1291 BBC #TT$V_PASSALL,UCB$L_DEVDEPEND(R5),25$; BR IF NOT PASSALL
0668 1292 INCL G^PM$SGL_PASSALL : INCREMENT PASSALL COUNT
0668 1293 :
0668 1294 : .ENDC
0668 1295 :
0668 1296 25$: BICB3 #^C<TT$M_PASSALL!TT$M_NOECHO>,UCB$L_DEVDEPEND(R5),R4;
0671 1297 INSV R4,#TT$V_ST_PASSALL,#2,4(R2) : RESET PASSALL AND NOECHO
0677 1298 EXTW #TT$V_ESCAPE,#1,UCB$L_DEVDEPEND(R5),R4 : GET CURRENT SETTING
```

03 44 A5 12 E1
F9BB' 30
68 A5 02 AA

7C A5 01FC 8F B0
54 78 A5 D0
53 58 A5 D0
53 3A A3 9B
3C A4 53 A2
7C A5 3C B0

54 44 A5 FC 8F 8B
04 A2 02 02 54 F0
54 44 A5 01 03 EE

| 04 | A2 | 01 | 0B | 54 | F0 | 067D | 1299 | INSV | R4, #TTY\$V ST ESCAPE, #1, 4(R2) | : | UPDATE IN STATE |
|------|----------|------|----|----|------|------|-------|---|----------------------------------|-------------------|-----------------|
| 04 | 48 | A5 | 12 | E1 | 0683 | 1300 | BBC | #Tf2\$V PASTHRU,UCB\$1_DEVDEPND2(R5),98\$ | : | IN PASS THRU MODE | |
| | | | | | 0688 | 1301 | | SET_STATE PASACL | | | |
| | | | | | 068C | 1302 | 98\$: | | | | |
| | | | | | 068C | 1303 | | | | | |
| | | | | | 068C | 1304 | | | | | |
| | | | | | 068C | 1305 | | | | | |
| | | | | | 068C | 1306 | | | | | |
| | | | | | 068C | 1307 | | | | | |
| | | | | | 068C | 1308 | | | | | |
| | | | | | 068C | 1309 | | | | | |
| | 53 | 58 | A5 | D0 | 0699 | 1310 | | | | | |
| | 54 | 78 | A5 | D0 | 069D | 1311 | | | | | |
| 012B | C5 | 3A | A4 | 90 | 06A1 | 1312 | | | | | |
| | | | | | 06A7 | 1313 | | | | | |
| | 3C | A3 | 0C | A3 | 06A7 | 1314 | | | | | |
| | 4C | A3 | 0B | A3 | 06AC | 1315 | | | | | |
| | 0B | A3 | 0B | A5 | 06B1 | 1316 | | | | | |
| | 30 | A3 | 7C | A5 | 06B6 | 1317 | | | | | |
| | 32 | A3 | 3C | A4 | 06BB | 1318 | | | | | |
| | | | | | 06C0 | 1319 | | | | | |
| | | 55 | 53 | D0 | 06C2 | 1320 | | | | | |
| | 53 | 10 | A3 | 7D | 06C5 | 1321 | | | | | |
| | | FE7B | CF | 9F | 06C9 | 1322 | | | | | |
| | | 3C | A5 | DD | 06CD | 1323 | | | | | |
| | 00000000 | | EF | 16 | 06D0 | 1324 | | | | | |
| | | | | | 06D6 | 1325 | | | | | |
| | | | | | 06D6 | 1326 | | | | | |
| | | | | | 06D6 | 1327 | | | | | |
| | 53 | 55 | | D0 | 06D6 | 1328 | | | | | |
| | | | | | 06D9 | 1329 | | | | | |
| | | | | | 06D9 | 1330 | | | | | |
| | | | | | 06D9 | 1331 | | | | | |
| | | | | | 06D9 | 1332 | | | | | |
| | | | | | 06D9 | 1333 | | | | | |
| | | | | | 06D9 | 1334 | | | | | |
| | | | | | 06D9 | 1335 | | | | | |
| | | | | | 06D9 | 1336 | | | | | |
| | | | | | 06D9 | 1337 | | | | | |
| | 55 | 1C | A3 | D0 | 06D9 | 1338 | | | | | |
| | 55 | 00A0 | C5 | D0 | 06DD | 1339 | | | | | |
| | 50 | 30 | A3 | D0 | 06E2 | 1340 | | | | | |
| | 54 | 3A | A3 | 9B | 06E6 | 1341 | | | | | |
| | 32 | A3 | 54 | A0 | 06EA | 1342 | | | | | |
| | 54 | 2C | A3 | D0 | 06EE | 1343 | | | | | |
| 21 | 20 | A3 | 0F | E1 | 06F2 | 1344 | | | | | |
| 39 | A3 | FF | 8F | 90 | 06F7 | 1345 | | | | | |
| 17 | 40 | A3 | 0A | E0 | 06FC | 1346 | | | | | |
| | 51 | 30 | A4 | 3C | 0701 | | | | | | |

```

OC A3 3C A3 D0 071C 1356      MOVL  IRP$L_TT_TERM(R3),IRP$L_PID(R3); RETURN IRP DATA
OB A3 4C A3 90 0721 1357      MOVBL IRP$L_TT_PRMT(R3),IRP$L_RMOD(R3);
30 A3 08 A4 B0 0726 1358      MOVBL TTY$L_RB_SIZE(R4),IRP$L_BOFF(R3); MAKE IT QUOTA
OF 48 A5 0C E0 0728 1359      BBS   #TT2$V_EDITING,UCB$L_DEVDEPND2(R5),40$; IF EDITING THEN
                                ; SAVE THE BUFFER.
                                0730 1360
                                0730 1361 READ$DONE:
                                0730 1362      BBS   #TT2$V_FALLBACK,UCB$L_DEVDEPND2(R5),200$; DO WE HAVE TO CHECK
4F 48 A5 0E E0 0730 1362      ; FOR INPUT FALLBACK
                                0735 1363 END_FALL:
                                0735 1364
                                0735 1365 TTY$DONE:
                                0735 1366      MOVL  IRP$L_UCB(R3),R5 ; RESTORE LOGICAL UCB ADDRESS
                                0739 1367      REQCOM ; COMPLETE REQUEST
                                073F 1368
                                073F 1369 ; SAVE THE COMMAND IF WE ARE IN EDITING, THE READ WAS SUCESSFUL AND
                                073F 1370 ; IT WAS NOT A NOECHO READ.
                                073F 1371
                                073F 1372 40$: CMPW  RO,#SS$_TIMEOUT ; ALLOW TIMEOUT ERRORS TO BE SAVED
                                0744 1373      BEQL  42$
                                0746 1374      BLBC  RO,READ$DONE ; READ NOT SUCCESSFUL THEN DON'T SAVE
                                0749 1375 42$: BITL  #TT$M_NOECHO!TT$M_PASSALL,UCB$L_DEVDEPEND(R5);DON'T COPY ON
                                074D 1376      BNEQ  READ$DONE ; PASSALL OR NOECHO
                                074F 1377      BITL  #TTY$M_ST_NOECHO!TTY$M_ST_PASALL!TTY$M_ST_NOFLTR,-
                                0755 1378      IRP$L_TT_STATE+4(R3) ; WERE WE PASS-ALL, NOECHO
                                0757 1379      BNEQ  READ$DONE ; OR NO FILTER THEN DON'T SAVE THIS BUFFER
                                0759 1380      PUSHR #M<R0,R1,R2,R3,R4,R5> ; SAVE THE REGISTERS OVER THE MOVE
                                075B 1381      MOVZWL TTY$L_RB_TXTOFF(R4),R0 ; GET THE LENGTH
                                075F 1382      BEQL  35$ ; IF THE LENGTH IS ZERO THEN DON'T SAVE
                                0761 1383 ; THE DATA
                                0761 1384      CMPL  #TTY$K_TA_RCLLEN,R0 ; DOES ALL THE DATA FIT?
                                0768 1385      BGEQ  30$ ; YES THEN CONTINUE ON
                                076A 1386      MOVL  #TTY$K_TA_RCLLEN,R0 ; ELSE USE THE WHOLE BFFER
                                0771 1387 30$: MOVL  UCB$L_TT_TYPAHD(R5),R1 ; GET THE ADDRESS OF THE TYPEAHEAD BUFFER
                                0776 1388      MOVW  RO,TTY$L_TA_RCLSZ(R1) ; KEEP THE SIZE CORRECTLY
                                077A 1389      MOVCL RO,@TTY$L_RB_TXT(R4),TTY$L_TA_RCL(R1); MOVE THE DATA IN
                                0780 1390 35$: POPR  #M<R0,R1,R2,R3,R4,R5> ; RESTORE THE REGISTERS AND
                                0782 1391 91$: BRB   READ$DONE
                                0784 1392
                                0784 1393 ; INPUT FALLBACK TABLE IMPLIMENTATION
                                0784 1394
                                0784 1395
                                0784 1396 200$:
                                0784 1397      PUSHR #M<R0,R1,R2,R3,R4,R5> ; SAVE THE REGISTERS OVER THE MOVE
51 00000000 3F BB 0784 1397      MOVL  @TTY$L_INPFALL,R1 ; ANY INPUT FALLBACK
                                0786 1398      BEQL  210$
                                078D 1399      MOVZWL TTY$L_RB_TXTOFF(R4),R0 ; GET THE LENGTH
                                078F 1400      BEQL  210$ ; IF THE LENGTH IS ZERO THEN DON'T SAVE
                                0793 1401      MOVCL RO,@TTY$L_RB_TXT(R4),#0,(R1);-
                                0795 1402      MOVCL RO,@TTY$L_RB_TXT(R4) ; MOVE THE DATA THRU THE FALLBACK TABLE
                                0798 1403      POPR  #M<R0,R1,R2,R3,R4,R5> ; RESTORE THE REGISTERS AND
61 00 00 B4 50 2E 0795 1402      210$:
                                0798 1403      220$: BRW
                                079E 1404      .Disable lsb
                                07A0 1405
                                07A3 1406

```

TTYSTRSTP
V04-000

- Terminal driver start/stop I/O routine 16-SEP-1984 02:18:30 VAX/VMS Macro V04-00 Page 35
TTYREADONE - READ OPERATION DONE 5-SEP-1984 04:17:09 [TTDRVR.SRC]TTYSTRSTP.MAR;1 (24)

07A3 1408
07A3 1409 .SBTTL End of module
07A3 1410
07A3 1411 .END

TTYSTRSTP
Symbol table

- Terminal driver start/stop I/O routine 16-SEP-1984 02:18:30 VAX/VMS Macro V04-00 Page 36
5-SEP-1984 04:17:09 [TTDRVR.SRC]TTYSTRSTP.MAR;1 (24)

| | | | | | | |
|------------------|------------|---|----|--------------------|------------|------|
| CLASS_MODEM_DIS | ***** | X | 02 | SS\$ ABORT | = 0000002C | |
| CNT | = 00000001 | | | SS\$ BADESCAPE | = 0000003C | |
| COMSPOST | ***** | X | 02 | SS\$ NOPRIV | = 00000024 | |
| DO_CONNECT | 00000037 | R | 02 | SS\$ NORMAL | = 00000001 | |
| DO_DISCONNECT | 000000A4 | R | 02 | SS\$ NOSUCHDEV | = 00000908 | |
| DO_EXIT | 00000422 | R | 02 | SS\$ PARTESCAPE | = 000001FC | |
| DO_HANGUP | 000000B5 | R | 02 | SS\$ TIMEOUT | = 0000022C | |
| DO_MAINT | 000000BF | R | 02 | START_PKT | 000004E6 | R 02 |
| DO_READ | 0000010D | R | 02 | T | = 00000005 | |
| DO_SET | 000001C1 | R | 02 | TRANSITION NOCHECK | ***** | X 02 |
| DO_SETC | 000001B5 | R | 02 | TTSC BAUD 9600 | = 0000000F | |
| DO_SETM | 000001B2 | R | 02 | TTSM_DS_DTR | = 00000002 | |
| DO_WRITE | 00000444 | R | 02 | TTSM_DS_RTS | = 00000010 | |
| END_FALL | 00000735 | R | 02 | TTSM_DS_SECTX | = 00000008 | |
| F | = 00000000 | | | TTSM_MBXDSABL | = 00010000 | |
| FIND BOL NOCLEAR | ***** | X | 02 | TTSM_MODEM | = 00200000 | |
| INSERT_PKT | 000004D9 | R | 02 | TTSM_NOBRDCST | = 00020000 | |
| IOSM_FCODE | = 0000003F | | | TTSM_NOECHO | = 00000002 | |
| IOSV_BREAKTHRU | = 00000009 | | | TTSM_ODD | = 00000080 | |
| IOSV_CANCTRLO | = 00000006 | | | TTSM_PARITY | = 00000040 | |
| IOSV_ENABLMBX | = 00000007 | | | TTSM_PASSALL | = 00000001 | |
| IOSV_EXTEND | = 0000000F | | | TTSM_REMOTE | = 00002000 | |
| IOSV_LOOP | = 00000007 | | | TTSV_ALTDISPAR | = 0000000A | |
| IOSV_LOOP_EXT | = 0000000C | | | TTSV_ALTFRAME | = 00000004 | |
| IOSV_NEWLINE | = 0000000A | | | TTSV_ALTRPAR | = 00000005 | |
| IOSV_PURGE | = 0000000B | | | TTSV_CRFILL | = 0000000A | |
| IOSV_SET MODEM | = 0000000A | | | TTSV_DISPARERR | = 00000009 | |
| IOSV-TT DISCON | = 0000000C | | | TTSV_EIGHTBIT | = 0000000F | |
| IOCSREQCOM | ***** | X | 02 | TTSV_ESCAPE | = 00000003 | |
| IPLS_QUEUEAST | = 00000006 | | | TTSV_LFFILL | = 0000000B | |
| IRPSB_RMOD | = 00000008 | | | TTSV_MODEM | = 00000015 | |
| IRPSL_ARB | = 00000058 | | | TTSV_PARITY | = 00000006 | |
| IRPSL_AST | = 00000010 | | | TTSV_PASSALL | = 00000000 | |
| IRPSL_IOST1 | = 00000038 | | | TTSV_READSYNC | = 00000012 | |
| IRPSL_IOST2 | = 0000003C | | | TTSV_REMOTE | = 0000000D | |
| IRPSL_MEDIA | = 00000038 | | | TTSV-TTSYNC | = 00000005 | |
| IRPSL_PID | = 0000000C | | | TTSV-TWOSTOP | = 00000008 | |
| IRPSL_SVAPTE | = 0000002C | | | TT2SM_ALTYPEAHD | = 00000080 | |
| IRPSL-TT TERM | = 0000003C | | | TT2SM_DCL MAILBX | = 00000200 | |
| IRPSL_UCB | = 0000001C | | | TT2SM_DISCONNECT | = 00020000 | |
| IRPSL_VAL5 | = 0000009C | | | TT2SM_DMA | = 00000040 | |
| IRPSQ-TT STATE | = 00000040 | | | TT2SM_XON | = 00000020 | |
| IRPS\$FCODE | = 00000006 | | | TT2SV_ALTYPEAHD | = 00000007 | |
| IRPSV_FCODE | = 00000000 | | | TT2SV_AUTOBAUD | = 00000001 | |
| IRPSW_BCNT | = 00000032 | | | TT2SV_DISCONNECT | = 00000011 | |
| IRPSW_BOFF | = 00000030 | | | TT2SV_DMA | = 00000006 | |
| IRPSW_FUNC | = 00000020 | | | TT2SV_EDITING | = 0000000C | |
| IRPSW-TT PRMPT | = 0000004C | | | TT2SV_FALLBACK | = 0000000E | |
| MODEMSC_INIT | = 00000000 | | | TT2SV_HANGUP | = 00000002 | |
| MODEMSC-SHUTDOWN | = 00000001 | | | TT2SV_LOCALECHO | = 00000000 | |
| NOPRIV_EXIT | 0000043C | R | 02 | TT2SV_MODHANGUP | = 00000003 | |
| PORT_STARTIO | = 00000000 | | | TT2SV-PASTHRU | = 00000012 | |
| PRVSV_LOG_IO | = 00000007 | | | TT2SV_SECURE | = 00000010 | |
| PRVSV_PHY_IO | = 00000016 | | | TT2SV-SETSPEED | = 00000008 | |
| QUEUE_LAST | 000004D5 | R | 02 | TT2SV_XON | = 00000005 | |
| QUEUE_PKT | 000004BC | R | 02 | TTY\$A_INPFALL | ***** | X 02 |
| READ\$DONE | 00000730 | R | 02 | TTY\$A_TA_RCL | = 00000018 | |

TTYSTRSTP
Symbol table

J 8

- Terminal driver start/stop I/O routine 16-SEP-1984 02:18:30 VAX/VMS Macro V04-00 Page 37
5-SEP-1984 04:17:09 [TTDRVR.SRC]TTYSTRSTP.MAR;1 (24)

| | | | |
|---------------------|------------|----|----|
| TTYSB_WB_FIPL | = 0000000B | | |
| TTYSB_WB_FORK | ***** | X | 02 |
| TTYSB_CR | = 0000000D | | |
| TTYSB_FC_SETC | = 00000003 | | |
| TTYSB_DONE | 00000735 | R | 02 |
| TTYSB_DS_SET | ***** | X | 02 |
| TTYSB_GETNEXTCHAR | ***** | X | 02 |
| TTYSB_GETNXTWRITE | 00000548 | RG | 02 |
| TTYSB_ER_ECHLINE | = 00000002 | | |
| TTYSB_TA_RCLLEN | = 00000100 | | |
| TTYSB_LOCK | ***** | X | 02 |
| TTYSB_RB_LIN | = 0000002C | | |
| TTYSB_RB_TXT | = 00000000 | | |
| TTYSB_WB_BLINK | = 00000004 | | |
| TTYSB_WB_END | = 00000020 | | |
| TTYSB_WB_FLINK | = 00000000 | | |
| TTYSB_WB_FR3 | = 00000010 | | |
| TTYSB_WB_IRP | = 00000024 | | |
| TTYSB_WB_RETADDR | = 0000002C | | |
| TTYSB_MAINT | ***** | X | 02 |
| TTYSB_PC_DMAENA | = 00000002 | | |
| TTYSB_PC_XOFENA | = 00000040 | | |
| TTYSB_ST_BACKSPACE | = 00000020 | | |
| TTYSB_ST_BADESC | = 00000100 | | |
| TTYSB_ST_CTRL0 | = 00000001 | | |
| TTYSB_ST_CTRLR | = 00040000 | | |
| TTYSB_ST_DEL | = 00000002 | | |
| TTYSB_ST_ECHAES | = 02000000 | | |
| TTYSB_ST_EDITING | = 00100000 | | |
| TTYSB_ST_EDITREAD | = 00000200 | | |
| TTYSB_ST_EOL | = 00000100 | | |
| TTYSB_ST_ESC | = 00000080 | | |
| TTYSB_ST_ESC_O | = 00004000 | | |
| TTYSB_ST_MULTI | = 00000040 | | |
| TTYSB_ST_NL | = 00000200 | | |
| TTYSB_ST_NOECHO | = 00000008 | | |
| TTYSB_ST_NOFLTR | = 00000040 | | |
| TTYSB_ST_OVERSTRIKE | = 00800000 | | |
| TTYSB_ST_PASALL | = 00000004 | | |
| TTYSB_ST_PRE | = 04000000 | | |
| TTYSB_ST_PROMPT | = 00000020 | | |
| TTYSB_ST_QUOTING | = 00400000 | | |
| TTYSB_ST_RDVERIFY | = 00000400 | | |
| TTYSB_ST_READ | = 00001000 | | |
| TTYSB_ST_RECALL | = 00000800 | | |
| TTYSB_ST_RECONNECT | = 10000000 | | |
| TTYSB_ST_REFRSH | = 00000400 | | |
| TTYSB_ST_SENDF | = 00000010 | | |
| TTYSB_ST_SKIPCRLF | = 00080000 | | |
| TTYSB_ST_SKIPLF | = 00002000 | | |
| TTYSB_ST_TERMORM | = 01000000 | | |
| TTYSB_ST_WRAP | = 00008000 | | |
| TTYSB_ST_WRITE | = 00000080 | | |
| TTYSB_ST_WRTALL | = 00000010 | | |
| TTYSB_PORGE_AHEAD | ***** | X | 02 |
| TTYSB_READONE | 0000063D | RG | 02 |
| TTYSB_RESTARTIO | ***** | X | 02 |

| | | | |
|---------------------|------------|----|----|
| TTYSB_RESUME | ***** | X | 02 |
| TTYSB_SETUP_READ | ***** | X | 02 |
| TTYSB_SET_LINE | ***** | X | 02 |
| TTYSB_STARTIO | 00000000 | RG | 02 |
| TTYSB_STARTOUTPUT | 00000532 | RG | 02 |
| TTYSB_SYNC | ***** | X | 02 |
| TTYSB_FD_DISCONNECT | = 00000002 | | |
| TTYSB_FD_GETAHD | = 00000001 | | |
| TTYSB_PC_DMAAVL | = 00000002 | | |
| TTYSB_PC_NOCRLF | = 00000007 | | |
| TTYSB_ST_ESCAPE | = 0000000B | | |
| TTYSB_ST_PASALL | = 00000002 | | |
| TTYSB_ST_RDVERIFY | = 0000000A | | |
| TTYSB_SX_BACKSPACE | = 00000005 | | |
| TTYSB_SX_BADESC | = 00000028 | | |
| TTYSB_SX_CTRL0 | = 00000020 | | |
| TTYSB_SX_CTRLR | = 00000032 | | |
| TTYSB_SX_DEL | = 00000021 | | |
| TTYSB_SX_ECHAES | = 00000039 | | |
| TTYSB_SX_EDITING | = 00000034 | | |
| TTYSB_SX_EDITREAD | = 00000009 | | |
| TTYSB_SX_EOL | = 00000008 | | |
| TTYSB_SX_ESC | = 00000027 | | |
| TTYSB_SX_ESC_O | = 0000002E | | |
| TTYSB_SX_MULTI | = 00000006 | | |
| TTYSB_SX_NL | = 00000029 | | |
| TTYSB_SX_NOECHO | = 00000023 | | |
| TTYSB_SX_NOFLTR | = 00000026 | | |
| TTYSB_SX_OVERSTRIKE | = 00000037 | | |
| TTYSB_SX_PASALL | = 00000022 | | |
| TTYSB_SX_PRE | = 0000003A | | |
| TTYSB_SX_PROMPT | = 00000025 | | |
| TTYSB_SX_QUOTING | = 00000036 | | |
| TTYSB_SX_RDVERIFY | = 0000000A | | |
| TTYSB_SX_READ | = 0000000C | | |
| TTYSB_SX_RECALL | = 0000000B | | |
| TTYSB_SX_RECONNECT | = 0000003C | | |
| TTYSB_SX_REFRSH | = 0000002A | | |
| TTYSB_SX_SENDF | = 00000004 | | |
| TTYSB_SX_SKIPCRLF | = 00000033 | | |
| TTYSB_SX_SKIPLF | = 0000002D | | |
| TTYSB_SX_TERMORM | = 00000038 | | |
| TTYSB_SX_WRAP | = 0000002F | | |
| TTYSB_SX_WRITE | = 00000007 | | |
| TTYSB_SX_WRTALL | = 00000024 | | |
| TTYSB_WRITEDONE | 00000587 | RG | 02 |
| TTYSB_WRITEPOST | 0000062A | RG | 02 |
| TTYSB_WRTSTARTIO | 00000452 | RG | 02 |
| TTYSB_RB_CPZORG | = 0000003A | | |
| TTYSB_RB_LINOFF | = 00000030 | | |
| TTYSB_RB_LINREST | = 00000032 | | |
| TTYSB_RB_MODE | = 00000044 | | |
| TTYSB_RB_SIZE | = 00000008 | | |
| TTYSB_RB_TXTOFF | = 0000003C | | |
| TTYSB_TA_RCLSIZ | = 00000014 | | |
| TTYSB_WB_BCNT | = 0000002A | | |
| TTYSB_WB_SIZE | = 00000008 | | |

TTYSTRSTP
Symbol table

- Terminal driver start/stop I/O routine 16-SEP-1984 02:18:30 VAX/VMS Macro V04-00 Page 38
5-SEP-1984 04:17:09 [TTDRVR.SRC]TTYSTRSTP.MAR;1 (24)

| | | | | | | | | | |
|---------------------|------------|---|----|----|--|--|--|------------|--|
| TTY\$W_WB_STATUS | = 00000028 | | | | | | | | |
| TTY\$XOFF | = ***** | X | 02 | X1 | | | | = 00000002 | |
| UCB\$B_DEVCLASS | = 00000040 | | | Z0 | | | | = 00000000 | |
| UCB\$B_DEVTYPE | = 00000041 | | | Z1 | | | | = 00000000 | |
| UCB\$B_FIPL | = 0000000B | | | | | | | | |
| UCB\$B_TT_CRFILL | = 000000F6 | | | | | | | | |
| UCB\$B_TT_DEPARI | = 000000EC | | | | | | | | |
| UCB\$B_TT_DETYPE | = 000000F0 | | | | | | | | |
| UCB\$B_TT_LASTC | = 000000FF | | | | | | | | |
| UCB\$B_TT_LFFILL | = 000000F7 | | | | | | | | |
| UCB\$B_TT_LINE | = 000000FE | | | | | | | | |
| UCB\$B_TT_MAINT | = 0000012A | | | | | | | | |
| UCB\$B_TT_OLDCPZORG | = 0000012B | | | | | | | | |
| UCB\$B_TT_OUTYPE | = 0000010B | | | | | | | | |
| UCB\$B_TT_PARITY | = 000000F8 | | | | | | | | |
| UCB\$B_DEVDEPEND | = 00000044 | | | | | | | | |
| UCB\$B_DEVDEPND2 | = 00000048 | | | | | | | | |
| UCB\$B_IRP | = 00000058 | | | | | | | | |
| UCB\$B_PDT | = 00000084 | | | | | | | | |
| UCB\$B_SVAPTE | = 00000078 | | | | | | | | |
| UCB\$B_TL_PHYUCB | = 000000A0 | | | | | | | | |
| UCB\$B_TT_DECHA1 | = 000000C8 | | | | | | | | |
| UCB\$B_TT_DECHAR | = 000000C4 | | | | | | | | |
| UCB\$B_TT_LOGUCB | = 000000C0 | | | | | | | | |
| UCB\$B_TT_PORT | = 00000118 | | | | | | | | |
| UCB\$B_TT_TYPAHD | = 000000E4 | | | | | | | | |
| UCB\$B_TT_WBLINK | = 000000D0 | | | | | | | | |
| UCB\$B_TT_WFLINK | = 000000CC | | | | | | | | |
| UCB\$B_TT_WRTBUF | = 000000D4 | | | | | | | | |
| UCB\$M_CANCEL | = 00000008 | | | | | | | | |
| UCB\$M_TIMEOUT | = 00000040 | | | | | | | | |
| UCB\$M_TT_DISPARERR | = 00000002 | | | | | | | | |
| UCB\$M_TT_DSBL | = 00000080 | | | | | | | | |
| UCB\$M_TT_LEN | = 00000018 | | | | | | | | |
| UCB\$M_TT_NOTIF | = 00000004 | | | | | | | | |
| UCB\$M_TT_ODD | = 00000080 | | | | | | | | |
| UCB\$M_TT_PARTY | = 00000040 | | | | | | | | |
| UCB\$M_TT_STOP | = 00000020 | | | | | | | | |
| UCB\$M_TT_TIMO | = 00000002 | | | | | | | | |
| UCB\$V_INT | = 00000001 | | | | | | | | |
| UCB\$V_TT_DISPARERR | = 00000001 | | | | | | | | |
| UCB\$V_TT_LEN | = 00000003 | | | | | | | | |
| UCB\$V_TT_USERFRAME | = 00000002 | | | | | | | | |
| UCB\$W_BOFF | = 0000007C | | | | | | | | |
| UCB\$W_DEVBUFSIZ | = 00000042 | | | | | | | | |
| UCB\$W_DEVSTS | = 00000068 | | | | | | | | |
| UCB\$W_STS | = 00000064 | | | | | | | | |
| UCB\$W_TT_CURSOR | = 000000FC | | | | | | | | |
| UCB\$W_TT_DESPEE | = 000000E8 | | | | | | | | |
| UCB\$W_TT_PRTCTL | = 00000122 | | | | | | | | |
| UCB\$W_TT_SPEED | = 000000F4 | | | | | | | | |
| W0 | = 00001F60 | | | | | | | | |
| W1 | = 07DC45E2 | | | | | | | | |
| WRITEPOST | 000005AB | R | 02 | | | | | | |
| WRTSTARTIO | 00000491 | R | 02 | | | | | | |
| X | = 000007DC | | | | | | | | |
| X0 | = 00000000 | | | | | | | | |

+-----+
! Psect synopsis !
+-----+

| PSECT name | Allocation | PSECT No. | Attributes |
|------------------|-------------------|-----------|---|
| ABS | 00000000 (0.) | 00 (0.) | NOPIC USR CON ABS LCL NOSHR NOEXE NORD NOWRT NOVEC BYTE |
| \$ABSS | 00000000 (0.) | 01 (1.) | NOPIC USR CON ABS LCL NOSHR EXE RD WRT NOVEC BYTE |
| \$\$\$115_DRIVER | 000007A3 (1955.) | 02 (2.) | NOPIC USR CON REL LCL NOSHR EXE RD WRT NOVEC LONG |

+-----+
! Performance indicators !
+-----+

| Phase | Page faults | CPU Time | Elapsed Time |
|------------------------|-------------|-------------|--------------|
| Initialization | 35 | 00:00:00.03 | 00:00:00.85 |
| Command processing | 118 | 00:00:00.33 | 00:00:03.16 |
| Pass 1 | 611 | 00:00:18.41 | 00:01:04.16 |
| Symbol table sort | 0 | 00:00:02.66 | 00:00:10.55 |
| Pass 2 | 264 | 00:00:03.99 | 00:00:13.95 |
| Symbol table output | 34 | 00:00:00.19 | 00:00:00.19 |
| Psect synopsis output | 2 | 00:00:00.02 | 00:00:00.67 |
| Cross-reference output | 0 | 00:00:00.00 | 00:00:00.00 |
| Assembler run totals | 1066 | 00:00:25.65 | 00:01:33.54 |

The working set limit was 2100 pages.
152906 bytes (299 pages) of virtual memory were used to buffer the intermediate code.
There were 130 pages of symbol table space allocated to hold 2384 non-local and 89 local symbols.
1411 source lines were read in Pass 1, producing 18 object records in Pass 2.
56 pages of virtual memory were used to define 53 macros.

+-----+
! Macro library statistics !
+-----+

| Macro library name | Macros defined |
|-------------------------------------|----------------|
| _\$255\$DUA28:[SYS.OBJ]LIB.MLB;1 | 22 |
| -\$255\$DUA28:[SYSLIB]STARLET.MLB;2 | 10 |
| TOTALS (all libraries) | 32 |

2769 GETS were required to define 32 macros.

There were no errors, warnings or information messages.

MACRO/LIS=LISS:TTYSTRSTP/OBJ=OBJ\$:TTYSTRSTP MSRC\$:TTYSTRSTP/UPDATE=(ENH\$:TTYSTRSTP)+EXECMLS/LIB

0404 AH-BT13A-SE
VAX/VMS V4.0

DIGITAL EQUIPMENT CORPORATION
CONFIDENTIAL AND PROPRIETARY